
RsAreg

Release 4.80.71.19

Rohde & Schwarz

Mar 25, 2024

CONTENTS:

1	Revision History	3
1.1	RsAreg	3
1.1.1	Version history	3
2	Getting Started	5
2.1	Introduction	5
2.2	Installation	6
2.3	Finding Available Instruments	7
2.4	Initiating Instrument Session	8
2.5	Plain SCPI Communication	11
2.6	Error Checking	13
2.7	Exception Handling	14
2.8	Transferring Files	15
2.9	Writing Binary Data	16
2.10	Transferring Big Data with Progress	16
2.11	Multithreading	18
2.12	Logging	21
3	Enums	25
3.1	AregDopplerUnit	25
3.2	AregPowSens	25
3.3	AregRadarPowIndicator	25
3.4	ByteOrder	25
3.5	CalDataMode	26
3.6	CalDataUpdate	26
3.7	Colour	26
3.8	DevExpFormat	26
3.9	DispKeybLockMode	26
3.10	ErFpowSensMapping	27
3.11	ErFpowSensSourceAreg	27
3.12	FormData	27
3.13	FormStatReg	27
3.14	FrontPanelLayout	27
3.15	HardCopyImageFormat	28
3.16	HardCopyRegion	28
3.17	IecDevId	28
3.18	IecTermMode	28
3.19	InclExcl	28
3.20	KbLayout	29
3.21	NetMode	29

3.22	Parity	29
3.23	PixelTestPredefined	29
3.24	PowSensDisplayPriority	29
3.25	PowSensFiltType	30
3.26	RecScpiCmdMode	30
3.27	RoscBandWidtExt	30
3.28	RoscFreqExt	30
3.29	RoscSourSetup	30
3.30	Rs232BdRate	31
3.31	Rs232StopBits	31
3.32	SelftLev	31
3.33	SelftLevWrite	31
3.34	SlopeType	31
3.35	StateExtended	32
3.36	Test	32
3.37	TestCalSelected	32
3.38	TimeProtocol	32
3.39	UnitAngleAreg	32
3.40	UnitLengthAreg	33
3.41	UnitPowSens	33
3.42	UnitRcsAreg	33
3.43	UnitShiftAreg	33
3.44	UnitSpeedAreg	33
3.45	UpdPolicyMode	34
4	RepCaps	35
4.1	HwInstance (Global)	35
4.2	BitNumberNull	35
4.3	Channel	35
4.4	Index	36
4.5	Level	36
4.6	ObjectIx	36
4.7	Subchannel	36
5	Examples	37
6	RsAreg API Structure	39
6.1	Calibration	42
6.1.1	All	43
6.1.1.1	Measure	44
6.1.2	Data	44
6.1.2.1	Factory	45
6.1.2.2	Update	45
6.1.2.2.1	Level	46
6.1.2.2.1.1	Force	46
6.1.3	Delay	47
6.1.3.1	Shutdown	48
6.1.4	Frequency	48
6.1.5	Level	49
6.1.5.1	Attenuator	49
6.1.6	Roscillator	50
6.1.6.1	Data	50
6.1.6.2	Store	51
6.1.7	Selected	52

	6.1.7.1	Measure	52
	6.1.8	Tselected	52
6.2	Device		53
	6.2.1	Settings	54
	6.2.1.1	Backup	54
	6.2.1.2	Restore	55
6.3	Diagnostic		55
	6.3.1	BgInfo	56
	6.3.2	Debug	56
	6.3.2.1	Page	57
	6.3.3	Eeprom<Channel>	58
	6.3.3.1	Bidentifier	58
	6.3.3.1.1	Catalog	59
	6.3.3.2	Customize	59
	6.3.3.3	Data	60
	6.3.3.3.1	Points	60
	6.3.4	Info	61
	6.3.4.1	Otime	61
	6.3.4.2	PoCount	62
	6.3.5	Measure	62
	6.3.5.1	Point	63
	6.3.6	Point	63
	6.3.6.1	Configuration	64
	6.3.7	Service	65
6.4	Display		66
	6.4.1	Annotation	67
	6.4.1.1	Amplitude	68
	6.4.1.2	Frequency	68
	6.4.2	Button	69
	6.4.3	Dialog	70
	6.4.4	Psave	71
	6.4.5	Touch	72
	6.4.5.1	Time	72
	6.4.6	Ukey	73
	6.4.6.1	Add	73
	6.4.7	Update	74
6.5	FormatPy		75
6.6	Fpanel		77
	6.6.1	Keyboard	77
6.7	HardCopy		77
	6.7.1	Device	78
	6.7.2	Execute	79
	6.7.3	File	79
	6.7.3.1	Name	80
	6.7.3.1.1	Auto	81
	6.7.3.1.1.1	Directory	82
	6.7.3.1.1.2	File	83
	6.7.3.1.1.3	Day	83
	6.7.3.1.1.4	Month	84
	6.7.3.1.1.5	Prefix	85
	6.7.3.1.1.6	Year	86
	6.7.4	Image	86
6.8	Initiate<Channel>		87
	6.8.1	Power	87

6.8.1.1	Continuous	87
6.9	Kboard	88
6.10	MassMemory	89
6.10.1	Catalog	92
6.10.1.1	Length	92
6.10.2	Dcatalog	93
6.10.2.1	Length	93
6.10.3	Load	94
6.10.3.1	State	94
6.10.4	Store	95
6.10.4.1	State	95
6.11	Memory	95
6.12	Read<Channel>	96
6.12.1	Power	96
6.13	Sense<Channel>	97
6.13.1	Power	97
6.13.1.1	Aperture	98
6.13.1.1.1	Default	98
6.13.1.1.1.1	State	98
6.13.1.1.2	Time	99
6.13.1.2	Correction	100
6.13.1.2.1	SpDevice	100
6.13.1.2.1.1	ListPy	100
6.13.1.2.1.2	Select	101
6.13.1.2.1.3	State	101
6.13.1.3	Direct	102
6.13.1.4	Display	103
6.13.1.4.1	Permanent	103
6.13.1.4.1.1	Priority	103
6.13.1.4.1.2	State	104
6.13.1.5	FilterPy	105
6.13.1.5.1	Length	105
6.13.1.5.1.1	Auto	105
6.13.1.5.1.2	User	106
6.13.1.5.2	NsRatio	107
6.13.1.5.2.1	Mtime	108
6.13.1.5.3	Sonce	108
6.13.1.5.4	TypePy	109
6.13.1.6	Frequency	110
6.13.1.7	Logging	111
6.13.1.7.1	State	111
6.13.1.8	Offset	112
6.13.1.8.1	State	113
6.13.1.9	Snumber	113
6.13.1.10	Source	114
6.13.1.11	Status	115
6.13.1.11.1	Device	115
6.13.1.12	Sversion	115
6.13.1.13	TypePy	116
6.13.1.14	Zero	116
6.13.2	Unit	117
6.13.2.1	Power	117
6.14	Slist	118
6.14.1	Clear	119

6.14.1.1	Lan	119
6.14.1.2	Usb	120
6.14.2	Element<Channel>	120
6.14.2.1	Mapping	121
6.14.3	Scan	121
6.14.3.1	Usensor	122
6.14.4	Sensor	123
6.14.4.1	Map	123
6.15	Source	123
6.15.1	AreGenerator	124
6.15.1.1	Channel	124
6.15.1.1.1	InputPy	125
6.15.1.1.2	Output	126
6.15.1.2	Object<ObjectIx>	126
6.15.1.2.1	All	127
6.15.1.2.2	Attenuation	127
6.15.1.2.3	Range	128
6.15.1.2.4	Rcs	128
6.15.1.2.5	SubChannel<Subchannel>	129
6.15.1.2.5.1	Doppler	129
6.15.1.2.5.2	Frequency	130
6.15.1.2.5.3	Speed	131
6.15.1.2.5.4	State	132
6.15.1.3	Osetup	133
6.15.1.3.1	MultiInstrument	133
6.15.1.3.1.1	Connect	133
6.15.1.3.1.2	Remove	134
6.15.1.3.1.3	Execute	134
6.15.1.3.1.4	Secondary<Index>	135
6.15.1.3.1.5	Add	135
6.15.1.3.1.6	Execute	136
6.15.1.3.1.7	Remove	136
6.15.1.4	Radar	137
6.15.1.4.1	Antenna	137
6.15.1.4.1.1	Custom	138
6.15.1.4.1.2	Reg	139
6.15.1.4.1.3	Gain	139
6.15.1.4.2	Base	140
6.15.1.4.3	Dbypass	141
6.15.1.4.4	Eirp	141
6.15.1.4.5	Ota	142
6.15.1.4.6	Power	143
6.15.1.5	Units	143
6.15.2	Bb	146
6.15.2.1	Path	146
6.15.3	Frequency	146
6.15.3.1	Cw	147
6.15.4	InputPy	148
6.15.4.1	Trigger	148
6.15.5	Modulation	149
6.15.5.1	All	149
6.15.6	Path	149
6.15.7	Power	150
6.15.7.1	Level	150

6.15.7.1.1	Immediate	150
6.15.7.2	Spc	151
6.15.7.2.1	Measure	151
6.15.7.2.2	Single	152
6.15.8	Roscillator	152
6.15.8.1	External	153
6.15.8.1.1	RfOff	154
6.15.8.2	Internal	155
6.15.8.2.1	Adjust	155
6.16	Status	156
6.16.1	Operation	157
6.16.1.1	Bit<BitNumberNull>	159
6.16.1.1.1	Condition	159
6.16.1.1.2	Enable	160
6.16.1.1.3	Event	161
6.16.1.1.4	Ntransition	161
6.16.1.1.5	Ptransition	162
6.16.2	Questionable	162
6.16.2.1	Bit<BitNumberNull>	165
6.16.2.1.1	Condition	165
6.16.2.1.2	Enable	166
6.16.2.1.3	Event	166
6.16.2.1.4	Ntransition	167
6.16.2.1.5	Ptransition	167
6.16.3	Queue	168
6.17	System	168
6.17.1	Beeper	175
6.17.2	Bios	176
6.17.3	Communicate	176
6.17.3.1	Gpib	176
6.17.3.1.1	Self	177
6.17.3.2	Hislip	178
6.17.3.3	Network	178
6.17.3.3.1	Common	179
6.17.3.3.2	IpAddress	181
6.17.3.3.2.1	Subnet	183
6.17.3.3.3	Restart	183
6.17.3.4	Scpi	184
6.17.3.4.1	Ethernet	184
6.17.3.5	Serial	184
6.17.3.6	Socket	186
6.17.3.7	Usb	186
6.17.4	Date	187
6.17.5	Device	188
6.17.6	DeviceFootprint	189
6.17.6.1	History	189
6.17.7	Dexchange	190
6.17.7.1	Execute	192
6.17.7.2	Template	192
6.17.7.2.1	Predefined	193
6.17.7.2.2	User	193
6.17.7.3	Transaction	194
6.17.8	Error	195
6.17.8.1	Code	196

6.17.8.2 History	197
6.17.9 ExtDevices	197
6.17.9.1 Update	198
6.17.9.1.1 Check	198
6.17.9.1.2 Needed	199
6.17.9.1.3 Tselected	199
6.17.10 Fpreset	200
6.17.11 Generic	201
6.17.12 Help	201
6.17.12.1 Syntax	202
6.17.13 Identification	203
6.17.14 Information	204
6.17.15 Linux	204
6.17.15.1 Kernel	204
6.17.16 Lock	205
6.17.16.1 Name	206
6.17.16.2 Owner	206
6.17.16.3 Release	207
6.17.16.4 Request	207
6.17.16.4.1 Shared	208
6.17.16.5 Shared	208
6.17.17 MassMemory	209
6.17.17.1 Path	209
6.17.18 Ntp	210
6.17.19 Package	210
6.17.19.1 ChartDisplay	210
6.17.19.2 GuiFramework	211
6.17.19.3 Qt	211
6.17.20 PciFpga	212
6.17.20.1 Update	212
6.17.20.1.1 Check	213
6.17.20.1.2 Needed	213
6.17.20.1.3 Tselected	214
6.17.21 Profiling	214
6.17.21.1 HwAccess	215
6.17.21.2 Logging	216
6.17.21.3 Module	217
6.17.21.4 Record	217
6.17.21.4.1 Count	219
6.17.21.4.2 Wrap	220
6.17.21.5 Tick	220
6.17.21.5.1 Enable	221
6.17.21.6 Tpoint	221
6.17.21.6.1 Catalog	222
6.17.22 Protect<Level>	222
6.17.22.1 State	223
6.17.23 Reboot	224
6.17.24 Restart	224
6.17.25 Srp	225
6.17.25.1 Discard	226
6.17.26 Security	227
6.17.26.1 Mmem	228
6.17.26.1.1 Protect	228
6.17.26.1.1.1 State	228

6.17.26.2	Network	229
6.17.26.2.1	Avahi	229
6.17.26.2.1.1	State	229
6.17.26.2.2	Ftp	230
6.17.26.2.2.1	State	230
6.17.26.2.3	Http	231
6.17.26.2.3.1	State	231
6.17.26.2.4	Raw	232
6.17.26.2.4.1	State	232
6.17.26.2.5	RemSupport	233
6.17.26.2.6	Rpc	233
6.17.26.2.6.1	State	234
6.17.26.2.7	Smb	234
6.17.26.2.7.1	State	235
6.17.26.2.8	Soe	235
6.17.26.2.8.1	State	236
6.17.26.2.9	Ssh	236
6.17.26.2.9.1	State	237
6.17.26.2.10	State	237
6.17.26.2.11	SwUpdate	238
6.17.26.2.11.1	State	238
6.17.26.2.12	Vnc	239
6.17.26.2.12.1	State	239
6.17.26.3	Sanitize	240
6.17.26.3.1	State	240
6.17.26.4	SuPolicy	241
6.17.26.5	UsbStorage	241
6.17.26.5.1	State	241
6.17.26.6	VolMode	242
6.17.26.6.1	State	242
6.17.27	Shutdown	243
6.17.28	SrData	244
6.17.29	Srexec	244
6.17.30	Srtime	245
6.17.30.1	Synchronize	246
6.17.31	Startup	246
6.17.32	Time	246
6.17.32.1	DaylightSavingTime	248
6.17.32.1.1	Rule	249
6.17.32.2	HrTimer	250
6.17.32.2.1	Absolute	250
6.17.32.3	Zone	251
6.17.33	Ulock	252
6.17.34	Undo	253
6.17.34.1	Hclear	253
6.17.34.2	Hid	254
6.17.34.3	Hlable	254
6.18	Test	255
6.18.1	Device	257
6.18.1.1	Internal	257
6.18.2	Pixel	257
6.18.3	Remote	259
6.18.3.1	Lockout	260
6.18.4	Res	260

6.18.5	Serror	261
6.18.5.1	Set	262
6.18.6	Sw	262
6.18.6.1	Scmd	262
6.18.7	Write	263
7	RsAreg Utilities	265
8	RsAreg Logger	271
9	RsAreg Events	273
10	Index	275
	Index	277



REVISION HISTORY

1.1 RsAreg

Rohde & Schwarz AREG100A automotive radar echo generator RsAreg instrument driver.

Basic Hello-World code:

```
from RsAreg import *  
  
instr = RsAreg('TCPIP::192.168.2.101::hislip0')  
idn = instr.query('*IDN?')  
print('Hello, I am: ' + idn)
```

Supported instruments: AREG

The package is hosted here: <https://pypi.org/project/RsAreg/>

Documentation: <https://RsAreg.readthedocs.io/>

Examples: <https://github.com/Rohde-Schwarz/Examples/>

1.1.1 Version history

Latest release notes summary: Documentation Fixes

Version 4.80.71

- Documentation Fixes

Version 4.80.70

- First release for FW 4.80.070

GETTING STARTED

2.1 Introduction



RsAreg is a Python remote-control communication module for Rohde & Schwarz SCPI-based Test and Measurement Instruments. It represents SCPI commands as fixed APIs and hence provides SCPI autocompletion and helps you to avoid common string typing mistakes.

Basic example of the idea:

SCPI command:

SYSTem:REFeRence:FREQuency:SOURce

Python module representation:

writing:

`driver.system.reference.frequency.source.set()`

reading:

`driver.system.reference.frequency.source.get()`

Check out this RsAreg example:

```
"""Getting started - how to work with RsAreg Python package.
This example performs basic RF settings on an R&S AREG instrument.
It shows the RsAreg calls and their corresponding SCPI commands.
Notice that the python RsAreg interfaces track the SCPI commands syntax."""
```

```
from RsAreg import *

# Open the session
areg = RsAreg('TCPIP::10.102.52.44::HISLIP', False, False)
# Greetings, stranger...
print(f'Hello, I am: {areg.utilities.idn_string}')

# SOURce:FREQuency:FIXed 2230000000
areg.source.frequency.cw.set_value(223E6)

areg.source.areGenerator.radar.base.set_attenuation(10)
```

(continues on next page)

(continued from previous page)

```
# Close the session
areg.close()
```

Couple of reasons why to choose this module over plain SCPI approach:

- Type-safe API using typing module
- You can still use the plain SCPI communication
- You can select which VISA to use or even not use any VISA at all
- Initialization of a new session is straight-forward, no need to set any other properties
- Many useful features are already implemented - reset, self-test, opc-synchronization, error checking, option checking
- Binary data blocks transfer in both directions
- Transfer of arrays of numbers in binary or ASCII format
- File transfers in both directions
- Events generation in case of error, sent data, received data, chunk data (for big files transfer)
- Multithreading session locking - you can use multiple threads talking to one instrument at the same time
- Logging feature tailored for SCPI communication - different for binary and ascii data

2.2 Installation

RsAreg is hosted on pypi.org. You can install it with pip (for example, `pip.exe` for Windows), or if you are using Pycharm (and you should be :-)) direct in the Pycharm **Package Management** GUI.

Preconditions

- Installed VISA. You can skip this if you plan to use only socket LAN connection. Download the Rohde & Schwarz VISA for Windows, Linux, Mac OS from [here](#)

Option 1 - Installing with `pip.exe` under Windows

- Start the command console: WinKey + R, type `cmd` and hit ENTER
- Change the working directory to the Python installation of your choice (adjust the user name and python version in the path):

```
cd c:\Users\John\AppData\Local\Programs\Python\Python37\Scripts
```
- Install with the command: `pip install RsAreg`

Option 2 - Installing in Pycharm

- In Pycharm Menu File->Settings->Project->Project Interpreter click on the '+' button on the top left (the last PyCharm version)
- Type RsAreg in the search box
- If you are behind a Proxy server, configure it in the Menu: File->Settings->Appearance->System Settings->HTTP Proxy

For more information about Rohde & Schwarz instrument remote control, check out our [Instrument Remote Control Web Series](#).

Option 3 - Offline Installation

If you are still reading the installation chapter, it is probably because the options above did not work for you - proxy problems, your boss saw the internet bill... Here are 6 steps for installing the RsAreg offline:

- Download this python script (**Save target as**): [rsinstrument_offline_install.py](#) This installs all the preconditions that the RsAreg needs.
- Execute the script in your offline computer (supported is python 3.6 or newer)
- Download the RsAreg package to your computer from the pypi.org: <https://pypi.org/project/RsAreg/#files> to for example c:\temp\
- Start the command line WinKey + R, type cmd and hit ENTER
- Change the working directory to the Python installation of your choice (adjust the user name and python version in the path):

```
cd c:\Users\John\AppData\Local\Programs\Python\Python37\Scripts
```

- Install with the command: `pip install c:\temp\RsAreg-4.80.71.19.tar`

2.3 Finding Available Instruments

Like the pyvisa's ResourceManager, the RsAreg can search for available instruments:

```
"""
Find the instruments in your environment
"""

from RsAreg import *

# Use the instr_list string items as resource names in the RsAreg constructor
instr_list = RsAreg.list_resources("?*")
print(instr_list)
```

If you have more VISAs installed, the one actually used by default is defined by a secret widget called Visa Conflict Manager. You can force your program to use a VISA of your choice:

```
"""
Find the instruments in your environment with the defined VISA implementation
"""
```

(continues on next page)

(continued from previous page)

```
from RsAreg import *

# In the optional parameter visa_select you can use for example 'rs' or 'ni'
# Rs Visa also finds any NRP-Zxx USB sensors
instr_list = RsAreg.list_resources('*.*', 'rs')
print(instr_list)
```

Tip: We believe our R&S VISA is the best choice for our customers. Here are the reasons why:

- Small footprint
 - Superior VXI-11 and HiSLIP performance
 - Integrated legacy sensors NRP-Zxx support
 - Additional VXI-11 and LXI devices search
 - Availability for Windows, Linux, Mac OS
-

2.4 Initiating Instrument Session

RsAreg offers four different types of starting your remote-control session. We begin with the most typical case, and progress with more special ones.

Standard Session Initialization

Initiating new instrument session happens, when you instantiate the RsAreg object. Below, is a simple Hello World example. Different resource names are examples for different physical interfaces.

```
"""
Simple example on how to use the RsAreg module for remote-controlling your instrument
Preconditions:

- Installed RsAreg Python module Version 4.80.71 or newer from pypi.org
- Installed VISA, for example R&S Visa 5.12 or newer
"""

from RsAreg import *

# A good practice is to assure that you have a certain minimum version installed
RsAreg.assert_minimum_version('4.80.71')
resource_string_1 = 'TCPIP::192.168.2.101::INSTR' # Standard LAN connection (also
↳ called VXI-11)
resource_string_2 = 'TCPIP::192.168.2.101::hislip0' # Hi-Speed LAN connection - see
↳ 1MA208
resource_string_3 = 'GPIB::20::INSTR' # GPIB Connection
resource_string_4 = 'USB::0x0AAD::0x0119::022019943::INSTR' # USB-TMC (Test and
↳ Measurement Class)

# Initializing the session
```

(continues on next page)

(continued from previous page)

```

driver = RsAreg(resource_string_1)

idn = driver.utilities.query_str('*IDN?')
print(f"\nHello, I am: '{idn}'")
print(f'RsAreg package version: {driver.utilities.driver_version}')
print(f'Visa manufacturer: {driver.utilities.visa_manufacturer}')
print(f'Instrument full name: {driver.utilities.full_instrument_model_name}')
print(f'Instrument installed options: {",".join(driver.utilities.instrument_options)}')

# Close the session
driver.close()

```

Note: If you are wondering about the missing ASRL1::INSTR, yes, it works too, but come on... it's 2023.

Do not care about specialty of each session kind; RsAreg handles all the necessary session settings for you. You immediately have access to many identification properties in the interface `driver.utilities`. Here are some of them:

- `idn_string`
- `driver_version`
- `visa_manufacturer`
- `full_instrument_model_name`
- `instrument_serial_number`
- `instrument_firmware_version`
- `instrument_options`

The constructor also contains optional boolean arguments `id_query` and `reset`:

```
driver = RsAreg('TCPIP::192.168.56.101::hislip0', id_query=True, reset=True)
```

- Setting `id_query` to `True` (default is `True`) checks, whether your instrument can be used with the RsAreg module.
- Setting `reset` to `True` (default is `False`) resets your instrument. It is equivalent to calling the `reset()` method.

Selecting a Specific VISA

Just like in the function `list_resources()`, the RsAreg allows you to choose which VISA to use:

```

"""
Choosing VISA implementation
"""

from RsAreg import *

# Force use of the Rs Visa. For NI Visa, use the "SelectVisa='ni'"
driver = RsAreg('TCPIP::192.168.56.101::INSTR', True, True, "SelectVisa='rs'")

idn = driver.utilities.query_str('*IDN?')
print(f"\nHello, I am: '{idn}'")

```

(continues on next page)

(continued from previous page)

```
print(f"\nI am using the VISA from: {driver.utilities.visa_manufacturer}")

# Close the session
driver.close()
```

No VISA Session

We recommend using VISA when possible preferably with HiSlip session because of its low latency. However, if you are a strict VISA denier, RsAreg has something for you too - **no Visa installation raw LAN socket**:

```
"""
Using RsAreg without VISA for LAN Raw socket communication
"""

from RsAreg import *

driver = RsAreg('TCPIP::192.168.56.101::5025::SOCKET', True, True, "SelectVisa='socket'")
print(f'Visa manufacturer: {driver.utilities.visa_manufacturer}')
print(f"\nHello, I am: '{driver.utilities.idn_string}'")

# Close the session
driver.close()
```

Warning: Not using VISA can cause problems by debugging when you want to use the communication Trace Tool. The good news is, you can easily switch to use VISA and back just by changing the constructor arguments. The rest of your code stays unchanged.

Simulating Session

If a colleague is currently occupying your instrument, leave him in peace, and open a simulating session:

```
driver = RsAreg('TCPIP::192.168.56.101::hislip0', True, True, "Simulate=True")
```

More option_string tokens are separated by comma:

```
driver = RsAreg('TCPIP::192.168.56.101::hislip0', True, True, "SelectVisa='rs', ↵
↵Simulate=True")
```

Shared Session

In some scenarios, you want to have two independent objects talking to the same instrument. Rather than opening a second VISA connection, share the same one between two or more RsAreg objects:

```
"""
Sharing the same physical VISA session by two different RsAreg objects
"""

from RsAreg import *
```

(continues on next page)

(continued from previous page)

```

driver1 = RsAreg('TCPIP::192.168.56.101::INSTR', True, True)
driver2 = RsAreg.from_existing_session(driver1)

print(f'driver1: {driver1.utilities.idn_string}')
print(f'driver2: {driver2.utilities.idn_string}')

# Closing the driver2 session does not close the driver1 session - driver1 is the
↪ 'session master'
driver2.close()
print(f'driver2: I am closed now')

print(f'driver1: I am still opened and working: {driver1.utilities.idn_string}')
driver1.close()
print(f'driver1: Only now I am closed.')

```

Note: The driver1 is the object holding the ‘master’ session. If you call the driver1.close(), the driver2 loses its instrument session as well, and becomes pretty much useless.

2.5 Plain SCPI Communication

After you have opened the session, you can use the instrument-specific part described in the RsAreg API Structure. If for any reason you want to use the plain SCPI, use the utilities interface’s two basic methods:

- write_str() - writing a command without an answer, for example *RST
- query_str() - querying your instrument, for example the *IDN? query

You may ask a question. Actually, two questions:

- Q1: Why there are not called write() and query() ?
- Q2: Where is the read() ?

Answer 1: Actually, there are - the write_str() / write() and query_str() / query() are aliases, and you can use any of them. We promote the _str names, to clearly show you want to work with strings. Strings in Python3 are Unicode, the bytes and string objects are not interchangeable, since one character might be represented by more than 1 byte. To avoid mixing string and binary communication, all the method names for binary transfer contain _bin in the name.

Answer 2: Short answer - you do not need it. Long answer - your instrument never sends unsolicited responses. If you send a set command, you use write_str(). For a query command, you use query_str(). So, you really do not need it...

Bottom line - if you are used to write() and query() methods, from pyvisa, the write_str() and query_str() are their equivalents.

Enough with the theory, let us look at an example. Simple write, and query:

```

"""
Basic string write_str / query_str
"""

```

(continues on next page)

(continued from previous page)

```

from RsAreg import *

driver = RsAreg('TCPIP::192.168.56.101::INSTR')
driver.utilities.write_str('*RST')
response = driver.utilities.query_str('*IDN?')
print(response)

# Close the session
driver.close()

```

This example is so-called “*University-Professor-Example*” - good to show a principle, but never used in praxis. The abovementioned commands are already a part of the driver’s API. Here is another example, achieving the same goal:

```

"""
Basic string write_str / query_str
"""

from RsAreg import *

driver = RsAreg('TCPIP::192.168.56.101::INSTR')
driver.utilities.reset()
print(driver.utilities.idn_string)

# Close the session
driver.close()

```

One additional feature we need to mention here: **VISA timeout**. To simplify, VISA timeout plays a role in each `query_xxx()`, where the controller (your PC) has to prevent waiting forever for an answer from your instrument. VISA timeout defines that maximum waiting time. You can set/read it with the `visa_timeout` property:

```

# Timeout in milliseconds
driver.utilities.visa_timeout = 3000

```

After this time, the RsAreg raises an exception. Speaking of exceptions, an important feature of the RsAreg is **Instrument Status Checking**. Check out the next chapter that describes the error checking in details.

For completion, we mention other string-based `write_xxx()` and `query_xxx()` methods - all in one example. They are convenient extensions providing type-safe float/boolean/integer setting/querying features:

```

"""
Basic string write_xxx / query_xxx
"""

from RsAreg import *

driver = RsAreg('TCPIP::192.168.56.101::INSTR')
driver.utilities.visa_timeout = 5000
driver.utilities.instrument_status_checking = True
driver.utilities.write_int('SWEEP:COUNT ', 10) # sending 'SWEEP:COUNT 10'
driver.utilities.write_bool('SOURCE:RF:OUTPUT:STATE ', True) # sending
↳ 'SOURCE:RF:OUTPUT:STATE ON'
driver.utilities.write_float('SOURCE:RF:FREQUENCY ', 1E9) # sending 'SOURCE:RF:FREQUENCY_
↳ 1000000000'

```

(continues on next page)

(continued from previous page)

```

sc = driver.utilities.query_int('SWEEP:COUNT?') # returning integer number sc=10
out = driver.utilities.query_bool('SOURCE:RF:OUTPUT:STATE?') # returning boolean
↳ out=True
freq = driver.utilities.query_float('SOURCE:RF:FREQUENCY?') # returning float number
↳ freq=1E9

# Close the session
driver.close()

```

Lastly, a method providing basic synchronization: `query_opc()`. It sends query ***OPC?** to your instrument. The instrument waits with the answer until all the tasks it currently has in a queue are finished. This way your program waits too, and this way it is synchronized with the actions in the instrument. Remember to have the VISA timeout set to an appropriate value to prevent the timeout exception. Here's the snippet:

```

driver.utilities.visa_timeout = 3000
driver.utilities.write_str("INIT")
driver.utilities.query_opc()

# The results are ready now to fetch
results = driver.utilities.query_str("FETCH:MEASUREMENT?")

```

Tip: Wait, there's more: you can send the ***OPC?** after each `write_xxx()` automatically:

```

# Default value after init is False
driver.utilities.opc_query_after_write = True

```

2.6 Error Checking

RsAreg pushes limits even further (internal R&S joke): It has a built-in mechanism that after each command/query checks the instrument's status subsystem, and raises an exception if it detects an error. For those who are already screaming: **Speed Performance Penalty!!!**, don't worry, you can disable it.

Instrument status checking is very useful since in case your command/query caused an error, you are immediately informed about it. Status checking has in most cases no practical effect on the speed performance of your program. However, if for example, you do many repetitions of short write/query sequences, it might make a difference to switch it off:

```

# Default value after init is True
driver.utilities.instrument_status_checking = False

```

To clear the instrument status subsystem of all errors, call this method:

```
driver.utilities.clear_status()
```

Instrument's status system error queue is clear-on-read. It means, if you query its content, you clear it at the same time. To query and clear list of all the current errors, use this snippet:

```
errors_list = driver.utilities.query_all_errors()
```

See the next chapter on how to react on errors.

2.7 Exception Handling

The base class for all the exceptions raised by the RsAreg is `RsInstrException`. Inherited exception classes:

- `ResourceError` raised in the constructor by problems with initiating the instrument, for example wrong or non-existing resource name
- `StatusException` raised if a command or a query generated error in the instrument's error queue
- `TimeoutException` raised if a visa timeout or an opc timeout is reached

In this example we show usage of all of them. Because it is difficult to generate an error using the instrument-specific SCPI API, we use plain SCPI commands:

```
"""
Showing how to deal with exceptions
"""

from RsAreg import *

driver = None
# Try-catch for initialization. If an error occurs, the ResourceError is raised
try:
    driver = RsAreg('TCPIP::10.112.1.179::hislip0')
except ResourceError as e:
    print(e.args[0])
    print('Your instrument is probably OFF...')
    # Exit now, no point of continuing
    exit(1)

# Dealing with commands that potentially generate errors OPTION 1:
# Switching the status checking OFF temporarily
driver.utilities.instrument_status_checking = False
driver.utilities.write_str('MY:MISSpelled:COMMAND')
# Clear the error queue
driver.utilities.clear_status()
# Status checking ON again
driver.utilities.instrument_status_checking = True

# Dealing with queries that potentially generate errors OPTION 2:
try:
    # You might want to reduce the VISA timeout to avoid long waiting
    driver.utilities.visa_timeout = 1000
    driver.utilities.query_str('MY:WRONG:QUERy?')
except StatusException as e:
    # Instrument status error
    print(e.args[0])
    print('Nothing to see here, moving on...')
except TimeoutException as e:
    # Timeout error
```

(continues on next page)

(continued from previous page)

```

print(e.args[0])
print('That took a long time...')

except RsInstrException as e:
    # RsInstrException is a base class for all the RsAreg exceptions
    print(e.args[0])
    print('Some other RsAreg error...')

finally:
    driver.utilities.visa_timeout = 5000
    # Close the session in any case
    driver.close()

```

Tip: General rules for exception handling:

- If you are sending commands that might generate errors in the instrument, for example deleting a file which does not exist, use the **OPTION 1** - temporarily disable status checking, send the command, clear the error queue and enable the status checking again.
- If you are sending queries that might generate errors or timeouts, for example querying measurement that can not be performed at the moment, use the **OPTION 2** - try/except with optionally adjusting the timeouts.

2.8 Transferring Files

Instrument -> PC

You definitely experienced it: you just did a perfect measurement, saved the results as a screenshot to an instrument's storage drive. Now you want to transfer it to your PC. With RsAreg, no problem, just figure out where the screenshot was stored on the instrument. In our case, it is `/var/user/instr_screenshot.png`:

```

driver.utilities.read_file_from_instrument_to_pc(
    r'/var/user/instr_screenshot.png',
    r'c:\temp\pc_screenshot.png')

```

PC -> Instrument

Another common scenario: Your cool test program contains a setup file you want to transfer to your instrument: Here is the RsAreg one-liner split into 3 lines:

```

driver.utilities.send_file_from_pc_to_instrument(
    r'c:\MyCoolTestProgram\instr_setup.sav',
    r'/var/appdata/instr_setup.sav')

```

2.9 Writing Binary Data

Writing from bytes

An example where you need to send binary data is a waveform file of a vector signal generator. First, you compose your `wform_data` as bytes, and then you send it with `write_bin_block()`:

```
# MyWaveform.wv is an instrument file name under which this data is stored
driver.utilities.write_bin_block(
    "SOUR:BB:ARB:WAV:DATA 'MyWaveform.wv'",",
    wform_data)
```

Note: Notice the `write_bin_block()` has two parameters:

- string parameter `cmd` for the SCPI command
 - bytes parameter `payload` for the actual binary data to send
-

Writing from PC files

Similar to querying binary data to a file, you can write binary data from a file. The second parameter is then the PC file path the content of which you want to send:

```
driver.utilities.write_bin_block_from_file(
    "SOUR:BB:ARB:WAV:DATA 'MyWaveform.wv'",",
    r"c:\temp\wform_data.wv")
```

2.10 Transferring Big Data with Progress

We can agree that it can be annoying using an application that shows no progress for long-lasting operations. The same is true for remote-control programs. Luckily, the RsAreg has this covered. And, this feature is quite universal - not just for big files transfer, but for any data in both directions.

RsAreg allows you to register a function (programmers fancy name is `callback`), which is then periodically invoked after transfer of one data chunk. You can define that chunk size, which gives you control over the callback invoke frequency. You can even slow down the transfer speed, if you want to process the data as they arrive (direction instrument -> PC).

To show this in praxis, we are going to use another *University-Professor-Example*: querying the `*IDN?` with chunk size of 2 bytes and delay of 200ms between each chunk read:

```
"""
Event handlers by reading
"""

from RsAreg import *
import time

def my_transfer_handler(args):
```

(continues on next page)

(continued from previous page)

```

"""Function called each time a chunk of data is transferred"""
# Total size is not always known at the beginning of the transfer
total_size = args.total_size if args.total_size is not None else "unknown"

print(f"Context: '{args.context}{'with opc' if args.opc_sync else ''}', "
      f"chunk {args.chunk_ix}, "
      f"transferred {args.transferred_size} bytes, "
      f"total size {total_size}, "
      f"direction {'reading' if args.reading else 'writing'}", "
      f"data '{args.data}')"

if args.end_of_transfer:
    print('End of Transfer')
    time.sleep(0.2)

driver = RsAreg('TCPIP::192.168.56.101::INSTR')

driver.events.on_read_handler = my_transfer_handler
# Switch on the data to be included in the event arguments
# The event arguments args.data will be updated
driver.events.io_events_include_data = True
# Set data chunk size to 2 bytes
driver.utilities.data_chunk_size = 2
driver.utilities.query_str('*IDN?')
# Unregister the event handler
driver.utilities.on_read_handler = None

# Close the session
driver.close()

```

If you start it, you might wonder (or maybe not): why is the `args.total_size = None`? The reason is, in this particular case the RsAreg does not know the size of the complete response up-front. However, if you use the same mechanism for transfer of a known data size (for example, file transfer), you get the information about the total size too, and hence you can calculate the progress as:

$$\text{progress [pct]} = 100 * \text{args.transferred_size} / \text{args.total_size}$$

Snippet of transferring file from PC to instrument, the rest of the code is the same as in the previous example:

```

driver.events.on_write_handler = my_transfer_handler
driver.events.io_events_include_data = True
driver.data_chunk_size = 1000
driver.utilities.send_file_from_pc_to_instrument(
    r'c:\MyCoolTestProgram\my_big_file.bin',
    r'/var/user/my_big_file.bin')
# Unregister the event handler
driver.events.on_write_handler = None

```

2.11 Multithreading

You are at the party, many people talking over each other. Not every person can deal with such crosstalk, neither can measurement instruments. For this reason, RsAreg has a feature of scheduling the access to your instrument by using so-called **Locks**. Locks make sure that there can be just one client at a time *talking* to your instrument. Talking in this context means completing one communication step - one command write or write/read or write/read/error check.

To describe how it works, and where it matters, we take three typical multithread scenarios:

One instrument session, accessed from multiple threads

You are all set - the lock is a part of your instrument session. Check out the following example - it will execute properly, although the instrument gets 10 queries at the same time:

```
"""
Multiple threads are accessing one RsAreg object
"""

import threading
from RsAreg import *

def execute(session):
    """Executed in a separate thread."""
    session.utilities.query_str('*IDN?')

driver = RsAreg('TCPIP::192.168.56.101::INSTR')
threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver, ))
    t.start()
    threads.append(t)
print('All threads started')

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

driver.close()
```

Shared instrument session, accessed from multiple threads

Same as the previous case, you are all set. The session carries the lock with it. You have two objects, talking to the same instrument from multiple threads. Since the instrument session is shared, the same lock applies to both objects causing the exclusive access to the instrument.

Try the following example:

```
"""
Multiple threads are accessing two RsAreg objects with shared session
```

(continues on next page)

(continued from previous page)

```

"""

import threading
from RsAreg import *

def execute(session: RsAreg, session_ix, index) -> None:
    """Executed in a separate thread."""
    print(f'{index} session {session_ix} query start...')
    session.utilities.query_str('*IDN?')
    print(f'{index} session {session_ix} query end')

driver1 = RsAreg('TCPIP::192.168.56.101::INSTR')
driver2 = RsAreg.from_existing_session(driver1)
driver1.utilities.visa_timeout = 200
driver2.utilities.visa_timeout = 200
# To see the effect of crosstalk, uncomment this line
# driver2.utilities.clear_lock()

threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver1, 1, i,))
    t.start()
    threads.append(t)
    t = threading.Thread(target=execute, args=(driver2, 2, i,))
    t.start()
    threads.append(t)
print('All threads started')

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

driver2.close()
driver1.close()

```

As you see, everything works fine. If you want to simulate some party crosstalk, uncomment the line `driver2.utilities.clear_lock()`. This causes the driver2 session lock to break away from the driver1 session lock. Although the driver1 still tries to schedule its instrument access, the driver2 tries to do the same at the same time, which leads to all the fun stuff happening.

Multiple instrument sessions accessed from multiple threads

Here, there are two possible scenarios depending on the instrument's VISA interface:

- You are lucky, because your instrument handles each remote session completely separately. An example of such instrument is SMW200A. In this case, you have no need for session locking.
- Your instrument handles all sessions with one set of in/out buffers. You need to lock the session for the duration of a talk. And you are lucky again, because the RsAreg takes care of it for you. The text below describes this scenario.

Run the following example:

```
"""
Multiple threads are accessing two RsAreg objects with two separate sessions
"""

import threading
from RsAreg import *

def execute(session: RsAreg, session_ix, index) -> None:
    """Executed in a separate thread."""
    print(f'{index} session {session_ix} query start...')
    session.utilities.query_str('*IDN?')
    print(f'{index} session {session_ix} query end')

driver1 = RsAreg('TCPIP::192.168.56.101::INSTR')
driver2 = RsAreg('TCPIP::192.168.56.101::INSTR')
driver1.utilities.visa_timeout = 200
driver2.utilities.visa_timeout = 200

# Synchronise the sessions by sharing the same lock
driver2.utilities.assign_lock(driver1.utilities.get_lock()) # To see the effect of
↳ crosstalk, comment this line

threads = []
for i in range(10):
    t = threading.Thread(target=execute, args=(driver1, 1, i,))
    t.start()
    threads.append(t)
    t = threading.Thread(target=execute, args=(driver2, 2, i,))
    t.start()
    threads.append(t)
print('All threads started')

# Wait for all threads to join this main thread
for t in threads:
    t.join()
print('All threads ended')

driver2.close()
driver1.close()
```

You have two completely independent sessions that want to talk to the same instrument at the same time. This will

not go well, unless they share the same session lock. The key command to achieve this is `driver2.utilities.assign_lock(driver1.utilities.get_lock())` Try to comment it and see how it goes. If despite commenting the line the example runs without issues, you are lucky to have an instrument similar to the SMW200A.

2.12 Logging

Yes, the logging again. This one is tailored for instrument communication. You will appreciate such handy feature when you troubleshoot your program, or just want to protocol the SCPI communication for your test reports.

What can you actually do with the logger?

- Write SCPI communication to a stream-like object, for example console or file, or both simultaneously
- Log only errors and skip problem-free parts; this way you avoid going through thousands lines of texts
- Investigate duration of certain operations to optimize your program's performance
- Log custom messages from your program

Let us take this basic example:

```
"""
Basic logging example to the console
"""

from RsAreg import *

driver = RsAreg('TCPIP::192.168.1.101::INSTR')

# Switch ON logging to the console.
driver.utilities.logger.log_to_console = True
driver.utilities.logger.mode = LoggingMode.On
driver.utilities.reset()

# Close the session
driver.close()
```

Console output:

10:29:10.819	TCPIP::192.168.1.101::INSTR	0.976 ms	Write: *RST
10:29:10.819	TCPIP::192.168.1.101::INSTR	1884.985 ms	Status check: OK
10:29:12.704	TCPIP::192.168.1.101::INSTR	0.983 ms	Query OPC: 1
10:29:12.705	TCPIP::192.168.1.101::INSTR	2.892 ms	Clear status: OK
10:29:12.708	TCPIP::192.168.1.101::INSTR	3.905 ms	Status check: OK
10:29:12.712	TCPIP::192.168.1.101::INSTR	1.952 ms	Close: Closing session

The columns of the log are aligned for better reading. Columns meaning:

- (1) Start time of the operation
- (2) Device resource name (you can set an alias)
- (3) Duration of the operation
- (4) Log entry

Tip: You can customize the logging format with `set_format_string()`, and set the maximum log entry length with the properties:

- `abbreviated_max_len_ascii`
- `abbreviated_max_len_bin`
- `abbreviated_max_len_list`

See the full logger help [here](#).

Notice the SCPI communication starts from the line `driver.utilities.reset()`. If you want to log the initialization of the session as well, you have to switch the logging ON already in the constructor:

```
driver = RsAreg('TCPIP::192.168.56.101::hislip0', options='LoggingMode=On')
```

Parallel to the console logging, you can log to a general stream. Do not fear the programmer's jargon... under the term **stream** you can just imagine a file. To be a little more technical, a stream in Python is any object that has two methods: `write()` and `flush()`. This example opens a file and sets it as logging target:

```
"""
Example of logging to a file
"""

from RsAreg import *

driver = RsAreg('TCPIP::192.168.1.101::INSTR')

# We also want to log to the console.
driver.utilities.logger.log_to_console = True

# Logging target is our file
file = open(r'c:\temp\my_file.txt', 'w')
driver.utilities.logger.set_logging_target(file)
driver.utilities.logger.mode = LoggingMode.On

# Instead of the 'TCPIP::192.168.1.101::INSTR', show 'MyDevice'
driver.utilities.logger.device_name = 'MyDevice'

# Custom user entry
driver.utilities.logger.info_raw('----- This is my custom log entry. ---- ')

driver.utilities.reset()

# Close the session
driver.close()

# Close the log file
file.close()
```

Tip: To make the log more compact, you can skip all the lines with Status check: OK:

```
driver.utilities.logger.log_status_check_ok = False
```

Hint: You can share the logging file between multiple sessions. In such case, remember to close the file only after you have stopped logging in all your sessions, otherwise you get a log write error.

For logging to a UDP port in addition to other log targets, use one of the lines:

```
driver.utilities.logger.log_to_udp = True
driver.utilities.logger.log_to_console_and_udp = True
```

You can select the UDP port to log to, the default is 49200:

```
driver.utilities.logger.udp_port = 49200
```

Another cool feature is logging only errors. To make this mode usefull for troubleshooting, you also want to see the circumstances which lead to the errors. Each driver elementary operation, for example, `write_str()`, can generate a group of log entries - let us call them **Segment**. In the logging mode **Errors**, a whole segment is logged only if at least one entry of the segment is an error.

The script below demonstrates this feature. We use a direct SCPI communication to send a misspelled SCPI command `*CLS`, which leads to instrument status error:

```
"""
Logging example to the console with only errors logged
"""

from RsAreg import *

driver = RsAreg('TCPIP::192.168.1.101::INSTR', options='LoggingMode=Errors')

# Switch ON logging to the console.
driver.utilities.logger.log_to_console = True

# Reset will not be logged, since no error occurred there
driver.utilities.reset()

# Now a misspelled command.
driver.utilities.write('*CLaS')

# A good command again, no logging here
idn = driver.utilities.query('*IDN?')

# Close the session
driver.close()
```

Console output:

```
12:11:02.879 TCPIP::192.168.1.101::INSTR 0.976 ms Write string: *CLaS
12:11:02.879 TCPIP::192.168.1.101::INSTR 6.833 ms Status check: StatusException:
Instrument error detected: Undefined header;
↪ *CLaS
```

Notice the following:

- Although the operation **Write string: *CLaS** finished without an error, it is still logged, because it provides the context for the actual error which occurred during the status checking right after.
- No other log entries are present, including the session initialization and close, because they were all error-free.

3.1 AregDopplerUnit

```
# Example value:  
value = enums.AregDopplerUnit.FREquency  
# All values (2x):  
FREquency | SPEed
```

3.2 AregPowSens

```
# Example value:  
value = enums.AregPowSens.SEN1  
# All values (5x):  
SEN1 | SEN2 | SEN3 | SEN4 | UDEfined
```

3.3 AregRadarPowIndicator

```
# Example value:  
value = enums.AregRadarPowIndicator.BAD  
# All values (4x):  
BAD | GOOD | OFF | WEAK
```

3.4 ByteOrder

```
# Example value:  
value = enums.ByteOrder.NORMal  
# All values (2x):  
NORMal | SWAPped
```

3.5 CalDataMode

```
# Example value:  
value = enums.CalDataMode.CUSTomer  
# All values (2x):  
CUSTomer | FACTory
```

3.6 CalDataUpdate

```
# Example value:  
value = enums.CalDataUpdate.BBFRC  
# All values (6x):  
BBFRC | FREquency | IALL | LEVel | LEVForced | RFFRC
```

3.7 Colour

```
# Example value:  
value = enums.Colour.GREen  
# All values (4x):  
GREen | NONE | RED | YELLow
```

3.8 DevExpFormat

```
# Example value:  
value = enums.DevExpFormat.CGPRedefined  
# All values (4x):  
CGPRedefined | CGUSer | SCPI | XML
```

3.9 DispKeybLockMode

```
# Example value:  
value = enums.DispKeybLockMode.DISabled  
# All values (5x):  
DISabled | DONLy | ENABled | TOFF | VNConly
```

3.10 ErFpowSensMapping

```
# First value:
value = enums.ErFpowSensMapping.SENS1
# Last value:
value = enums.ErFpowSensMapping.UNMapped
# All values (9x):
SENS1 | SENS2 | SENS3 | SENS4 | SENSor1 | SENSor2 | SENSor3 | SENSor4
UNMapped
```

3.11 ErFpowSensSourceAreg

```
# Example value:
value = enums.ErFpowSensSourceAreg.USER
# All values (1x):
USER
```

3.12 FormData

```
# Example value:
value = enums.FormData.ASCii
# All values (2x):
ASCii | PACKed
```

3.13 FormStatReg

```
# Example value:
value = enums.FormStatReg.ASCii
# All values (4x):
ASCii | BINary | HEXadecimal | OCTal
```

3.14 FrontPanelLayout

```
# Example value:
value = enums.FrontPanelLayout.DIGits
# All values (2x):
DIGits | LETTers
```

3.15 HardCopyImageFormat

```
# Example value:  
value = enums.HardCopyImageFormat.BMP  
# All values (4x):  
BMP | JPG | PNG | XPM
```

3.16 HardCopyRegion

```
# Example value:  
value = enums.HardCopyRegion.ALL  
# All values (2x):  
ALL | DIALog
```

3.17 IecDevId

```
# Example value:  
value = enums.IecDevId.AUTO  
# All values (2x):  
AUTO | USER
```

3.18 IecTermMode

```
# Example value:  
value = enums.IecTermMode.EOI  
# All values (2x):  
EOI | STANdard
```

3.19 InclExcl

```
# Example value:  
value = enums.InclExcl.EXCLude  
# All values (2x):  
EXCLude | INCLUDE
```


3.20 KbLayout

```
# First value:
value = enums.KbLayout.CHINese
# Last value:
value = enums.KbLayout.SWEDish
# All values (20x):
CHINese | DANish | DUTBe | DUTCh | ENGLish | ENGUK | ENGUS | FINNish
FREBe | FRECa | FRENch | GERMan | ITALian | JAPanese | KOREan | NORWegian
PORTuguese | RUSSian | SPANish | SWEDish
```

3.21 NetMode

```
# Example value:
value = enums.NetMode.AUTO
# All values (2x):
AUTO | STATic
```

3.22 Parity

```
# Example value:
value = enums.Parity.EVEN
# All values (3x):
EVEN | NONE | ODD
```

3.23 PixelTestPredefined

```
# First value:
value = enums.PixelTestPredefined.AUTO
# Last value:
value = enums.PixelTestPredefined.WHITE
# All values (9x):
AUTO | BLACK | BLUE | GR25 | GR50 | GR75 | GREen | RED
WHITE
```

3.24 PowSensDisplayPriority

```
# Example value:
value = enums.PowSensDisplayPriority.AVERage
# All values (2x):
AVERage | PEAK
```

3.25 PowSensFiltType

```
# Example value:  
value = enums.PowSensFiltType.AUTO  
# All values (3x):  
AUTO | NSRatio | USER
```

3.26 RecScpiCmdMode

```
# Example value:  
value = enums.RecScpiCmdMode.AUTO  
# All values (4x):  
AUTO | DAUTO | MANual | OFF
```

3.27 RoscBandWidtExt

```
# Example value:  
value = enums.RoscBandWidtExt.NARRow  
# All values (2x):  
NARRow | WIDE
```

3.28 RoscFreqExt

```
# Example value:  
value = enums.RoscFreqExt._10MHZ  
# All values (3x):  
_10MHZ | _13MHZ | _5MHZ
```

3.29 RoscSourSetup

```
# Example value:  
value = enums.RoscSourSetup.ELoop  
# All values (3x):  
ELoop | EXternal | INternal
```

3.30 Rs232BdRate

```
# Example value:  
value = enums.Rs232BdRate._115200  
# All values (7x):  
_115200 | _19200 | _2400 | _38400 | _4800 | _57600 | _9600
```

3.31 Rs232StopBits

```
# Example value:  
value = enums.Rs232StopBits._1  
# All values (2x):  
_1 | _2
```

3.32 SelftLev

```
# Example value:  
value = enums.SelftLev.CUSTomer  
# All values (3x):  
CUSTomer | PRODUCTION | SERVICE
```

3.33 SelftLevWrite

```
# Example value:  
value = enums.SelftLevWrite.CUSTomer  
# All values (4x):  
CUSTomer | NONE | PRODUCTION | SERVICE
```

3.34 SlopeType

```
# Example value:  
value = enums.SlopeType.NEGative  
# All values (2x):  
NEGative | POSitive
```

3.35 StateExtended

```
# Example value:  
value = enums.StateExtended.DEFAULT  
# All values (3x):  
DEFAULT | OFF | ON
```

3.36 Test

```
# Example value:  
value = enums.Test._0  
# All values (4x):  
_0 | _1 | RUNNING | STOPPED
```

3.37 TestCalSelected

```
# Example value:  
value = enums.TestCalSelected._0  
# All values (2x):  
_0 | _1
```

3.38 TimeProtocol

```
# Example value:  
value = enums.TimeProtocol._0  
# All values (6x):  
_0 | _1 | NONE | NTP | OFF | ON
```

3.39 UnitAngleAreg

```
# Example value:  
value = enums.UnitAngleAreg.DEGREE  
# All values (2x):  
DEGREE | RADIANT
```

3.40 UnitLengthAreg

```
# Example value:  
value = enums.UnitLengthAreg.CM  
# All values (3x):  
CM | FT | M
```

3.41 UnitPowSens

```
# Example value:  
value = enums.UnitPowSens.DBM  
# All values (3x):  
DBM | DBUV | WATT
```

3.42 UnitRcsAreg

```
# Example value:  
value = enums.UnitRcsAreg.DBSM  
# All values (2x):  
DBSM | SM
```

3.43 UnitShiftAreg

```
# Example value:  
value = enums.UnitShiftAreg.HZ  
# All values (3x):  
HZ | KHZ | MHZ
```

3.44 UnitSpeedAreg

```
# Example value:  
value = enums.UnitSpeedAreg.KMH  
# All values (3x):  
KMH | MPH | MPS
```

3.45 UpdPolicyMode

```
# Example value:  
value = enums.UpdPolicyMode.CONFirm  
# All values (3x):  
CONFirm | IGNore | STRict
```

REPCAPS

4.1 HwInstance (Global)

```
# Setting:
driver.repcap_hwInstance_set(repcap.HwInstance.InstA)
# Range:
InstA .. InstH
# All values (8x):
InstA | InstB | InstC | InstD | InstE | InstF | InstG | InstH
```

4.2 BitNumberNull

```
# First value:
value = repcap.BitNumberNull.Nr0
# Range:
Nr0 .. Nr15
# All values (16x):
Nr0 | Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7
Nr8 | Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15
```

4.3 Channel

```
# First value:
value = repcap.Channel.Nr1
# Range:
Nr1 .. Nr64
# All values (64x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
Nr17 | Nr18 | Nr19 | Nr20 | Nr21 | Nr22 | Nr23 | Nr24
Nr25 | Nr26 | Nr27 | Nr28 | Nr29 | Nr30 | Nr31 | Nr32
Nr33 | Nr34 | Nr35 | Nr36 | Nr37 | Nr38 | Nr39 | Nr40
Nr41 | Nr42 | Nr43 | Nr44 | Nr45 | Nr46 | Nr47 | Nr48
Nr49 | Nr50 | Nr51 | Nr52 | Nr53 | Nr54 | Nr55 | Nr56
Nr57 | Nr58 | Nr59 | Nr60 | Nr61 | Nr62 | Nr63 | Nr64
```

4.4 Index

```
# First value:
value = repcap.Index.Nr1
# Range:
Nr1 .. Nr64
# All values (64x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
Nr17 | Nr18 | Nr19 | Nr20 | Nr21 | Nr22 | Nr23 | Nr24
Nr25 | Nr26 | Nr27 | Nr28 | Nr29 | Nr30 | Nr31 | Nr32
Nr33 | Nr34 | Nr35 | Nr36 | Nr37 | Nr38 | Nr39 | Nr40
Nr41 | Nr42 | Nr43 | Nr44 | Nr45 | Nr46 | Nr47 | Nr48
Nr49 | Nr50 | Nr51 | Nr52 | Nr53 | Nr54 | Nr55 | Nr56
Nr57 | Nr58 | Nr59 | Nr60 | Nr61 | Nr62 | Nr63 | Nr64
```

4.5 Level

```
# First value:
value = repcap.Level.Nr1
# Range:
Nr1 .. Nr16
# All values (16x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
```

4.6 ObjectIx

```
# First value:
value = repcap.ObjectIx.Nr1
# Range:
Nr1 .. Nr12
# All values (12x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12
```

4.7 Subchannel

```
# First value:
value = repcap.Subchannel.Nr1
# Range:
Nr1 .. Nr16
# All values (16x):
Nr1 | Nr2 | Nr3 | Nr4 | Nr5 | Nr6 | Nr7 | Nr8
Nr9 | Nr10 | Nr11 | Nr12 | Nr13 | Nr14 | Nr15 | Nr16
```


EXAMPLES

For more examples, visit our [Rohde & Schwarz Github repository](#).

```
"""Getting started - how to work with RsAreg Python package.  
This example performs basic RF settings on an R&S AREG instrument.  
It shows the RsAreg calls and their corresponding SCPI commands.  
Notice that the python RsAreg interfaces track the SCPI commands syntax."""
```

```
from RsAreg import *  
  
# Open the session  
areg = RsAreg('TCPIP::10.102.52.44::HISLIP', False, False)  
# Greetings, stranger...  
print(f'Hello, I am: {areg.utilities.idn_string}')  
# SOURCE:FREQUENCY:FIXed 2230000000  
areg.source.frequency.cw.set_value(223E6)  
  
areg.source.areGenerator.radar.base.set_attenuation(10)  
  
# Close the session  
areg.close()
```


RSAREG API STRUCTURE

Global RepCaps

```
driver = RsAreg('TCPIP::192.168.2.101::hislip0')
# HwInstance range: InstA .. InstH
rc = driver.repcap_hwInstance_get()
driver.repcap_hwInstance_set(repcap.HwInstance.InstA)
```

class RsAreg(*resource_name: str, id_query: bool = True, reset: bool = False, options: str = None, direct_session: object = None*)

407 total commands, 18 Subgroups, 0 group commands

Initializes new RsAreg session.

Parameter options tokens examples:

- **Simulate=True** - starts the session in simulation mode. Default: **False**
- **SelectVisa=socket** - uses no VISA implementation for socket connections - you do not need any VISA-C installation
- **SelectVisa=rs** - forces usage of RohdeSchwarz Visa
- **SelectVisa=ivi** - forces usage of National Instruments Visa
- **QueryInstrumentStatus = False** - same as **driver.utilities.instrument_status_checking = False**. Default: **True**
- **WriteDelay = 20, ReadDelay = 5** - Introduces delay of 20ms before each write and 5ms before each read. Default: **0ms** for both
- **OpcWaitMode = OpcQuery** - mode for all the opc-synchronised write/reads. Other modes: **StbPolling, StbPollingSlow, StbPollingSuperSlow**. Default: **StbPolling**
- **AddTermCharToWriteBinBlock = True** - Adds one additional LF to the end of the binary data (some instruments require that). Default: **False**
- **AssureWriteWithTermChar = True** - Makes sure each command/query is terminated with termination character. Default: Interface dependent
- **TerminationCharacter = "\r"** - Sets the termination character for reading. Default: **\n** (LineFeed or LF)
- **DataChunkSize = 10E3** - Maximum size of one write/read segment. If transferred data is bigger, it is split to more segments. Default: **1E6** bytes
- **OpcTimeout = 10000** - same as **driver.utilities.opc_timeout = 10000**. Default: **30000ms**
- **VisaTimeout = 5000** - same as **driver.utilities.visa_timeout = 5000**. Default: **10000ms**

- `ViClearExeMode` = Disabled - `viClear()` execution mode. Default: `execute_on_all`
- `OpcQueryAfterWrite` = True - same as `driver.utilities.opc_query_after_write` = True. Default: False
- `StbInErrorCheck` = False - if true, the driver checks errors with `*STB?` If false, it uses `SYST:ERR?`. Default: True
- `ScpiQuotes` = double'. - for SCPI commands, you can define how strings are quoted. With single or double quotes. Possible values: `single` | `double` | `{char}`. Default: ```single`
- `LoggingMode` = On - Sets the logging status right from the start. Default: Off
- `LoggingName` = 'MyDevice' - Sets the name to represent the session in the log entries. Default: 'resource_name'
- `LogToGlobalTarget` = True - Sets the logging target to the class-property previously set with `RsAreg.set_global_logging_target()` Default: False
- `LoggingToConsole` = True - Immediately starts logging to the console. Default: False
- `LoggingToUdp` = True - Immediately starts logging to the UDP port. Default: False
- `LoggingUdpPort` = 49200 - UDP port to log to. Default: 49200

Parameters

- **resource_name** – VISA resource name, e.g. 'TCPIP::192.168.2.1::INSTR'
- **id_query** – if True, the instrument's model name is verified against the models supported by the driver and eventually throws an exception.
- **reset** – Resets the instrument (sends `*RST` command) and clears its status sybssystem.
- **options** – string tokens alternating the driver settings.
- **direct_session** – Another driver object or pyVisa object to reuse the session instead of opening a new session.

static `assert_minimum_version(min_version: str) → None`

Asserts that the driver version fulfills the minimum required version you have entered. This way you make sure your installed driver is of the entered version or newer.

classmethod `clear_global_logging_relative_timestamp() → None`

Clears the global relative timestamp. After this, all the instances using the global relative timestamp continue logging with the absolute timestamps.

close() → None

Closes the active RsAreg session.

classmethod `from_existing_session(session: object, options: str = None) → RsAreg`

Creates a new RsAreg object with the entered 'session' reused.

Parameters

- **session** – can be another driver or a direct pyvisa session.
- **options** – string tokens alternating the driver settings.

classmethod `get_global_logging_relative_timestamp() → datetime`

Returns global common relative timestamp for log entries.

classmethod `get_global_logging_target()`

Returns global common target stream.

get_session_handle() → object

Returns the underlying session handle.

get_total_execution_time() → timedelta

Returns total time spent by the library on communicating with the instrument. This time is always shorter than `get_total_time()`, since it does not include gaps between the communication. You can reset this counter with `reset_time_statistics()`.

get_total_time() → timedelta

Returns total time spent by the library on communicating with the instrument. This time is always shorter than `get_total_time()`, since it does not include gaps between the communication. You can reset this counter with `reset_time_statistics()`.

static `list_resources(expression: str = '?*::INSTR', visa_select: str = None)` → List[str]

Finds all the resources defined by the expression

- `'?*' - matches all the available instruments`
- `'USB::?*' - matches all the USB instruments`
- `'TCPIP::192?*' - matches all the LAN instruments with the IP address starting with 192`

Parameters

- **expression** – see the examples in the function
- **visa_select** – optional parameter selecting a specific VISA. Examples: `'@ivi'`, `'@rs'`

reset_time_statistics() → None

Resets all execution and total time counters. Affects the results of `get_total_time()` and `get_total_execution_time()`

restore_all_repcaps_to_default() → None

Sets all the Group and Global repcaps to their initial values

classmethod `set_global_logging_relative_timestamp(timestamp: datetime)` → None

Sets global common relative timestamp for log entries. To use it, call the following:
`io.utilities.logger.set_relative_timestamp_global()`

classmethod `set_global_logging_relative_timestamp_now()` → None

Sets global common relative timestamp for log entries to this moment. To use it, call the following:
`io.utilities.logger.set_relative_timestamp_global()`.

classmethod `set_global_logging_target(target)` → None

Sets global common target stream that each instance can use. To use it, call the following:
`io.utilities.logger.set_logging_target_global()`. If an instance uses global logging target, it automatically uses the global relative timestamp (if set). You can set the target to None to invalidate it.

Subgroups

6.1 Calibration

SCPI Commands :

```
CALibration<HW>:CONTinueonerror  
CALibration<HW>:DEBug
```

class CalibrationCls

Calibration commands group definition. 24 total commands, 8 Subgroups, 2 group commands

get_continue_on_error() → bool

```
# SCPI: CALibration<HW>:CONTinueonerror  
value: bool = driver.calibration.get_continue_on_error()
```

Continues the calibration even though an error was detected. By default adjustments are aborted on error.

return
state: 0| 1| OFF| ON

set_continue_on_error(state: bool) → None

```
# SCPI: CALibration<HW>:CONTinueonerror  
driver.calibration.set_continue_on_error(state = False)
```

Continues the calibration even though an error was detected. By default adjustments are aborted on error.

param state
0| 1| OFF| ON

set_debug(state: bool) → None

```
# SCPI: CALibration<HW>:DEBug  
driver.calibration.set_debug(state = False)
```

No command help available

param state
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently  
group2 = driver.calibration.clone()
```

Subgroups

6.1.1 All

SCPI Commands :

```
CALibration<HW>:ALL:DATE
CALibration<HW>:ALL:INformation
CALibration<HW>:ALL:TEMP
CALibration<HW>:ALL:TIME
```

class AllCls

All commands group definition. 5 total commands, 1 Subgroups, 4 group commands

get_date() → str

```
# SCPI: CALibration<HW>:ALL:DATE
value: str = driver.calibration.all.get_date()
```

Queries the date of the most recently executed full adjustment.

```
return
    date: string
```

get_information() → str

```
# SCPI: CALibration<HW>:ALL:INformation
value: str = driver.calibration.all.get_information()
```

Queries the current state of the internal adjustment.

```
return
    cal_info_text: string
```

get_temp() → str

```
# SCPI: CALibration<HW>:ALL:TEMP
value: str = driver.calibration.all.get_temp()
```

Queries the temperature deviation compared to the calibration temperature.

```
return
    temperature: string
```

get_time() → str

```
# SCPI: CALibration<HW>:ALL:TIME
value: str = driver.calibration.all.get_time()
```

Queries the time elapsed since the last full adjustment.

```
return
    time: string
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.all.clone()
```

Subgroups

6.1.1.1 Measure

SCPI Command :

```
CALibration:ALL:[MEASure]
```

class MeasureCls

Measure commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(force: str = None) → bool

```
# SCPI: CALibration:ALL:[MEASure]
value: bool = driver.calibration.all.measure.get(force = 'abc')
```

Starts all internal adjustments that do not need external measuring equipment.

param force
string

return
measure: 0| 1| OFF| ON

6.1.2 Data

SCPI Command :

```
CALibration:DATA:EXPort
```

class DataCls

Data commands group definition. 4 total commands, 2 Subgroups, 1 group commands

export() → None

```
# SCPI: CALibration:DATA:EXPort
driver.calibration.data.export()
```

No command help available

export_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: CALibration:DATA:EXPort
driver.calibration.data.export_with_opc()
```

No command help available

Same as export, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.data.clone()
```

Subgroups**6.1.2.1 Factory****SCPI Command :**

```
CALibration:DATA:FACTory:DATE
```

class FactoryCls

Factory commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_date() → str

```
# SCPI: CALibration:DATA:FACTory:DATE
value: str = driver.calibration.data.factory.get_date()
```

Queries the date of the last factory calibration.

return
date: string

6.1.2.2 Update**SCPI Command :**

```
CALibration<HW>:DATA:UPDate
```

class UpdateCls

Update commands group definition. 2 total commands, 1 Subgroups, 1 group commands

set_value(action_sel: CalDataUpdate) → None

```
# SCPI: CALibration<HW>:DATA:UPDate
driver.calibration.data.update.set_value(action_sel = enums.CalDataUpdate.BBFRC)
```

No command help available

param action_sel
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.data.update.clone()
```

Subgroups

6.1.2.2.1 Level

class LevelCls

Level commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.data.update.level.clone()
```

Subgroups

6.1.2.2.1.1 Force

SCPI Command :

```
CALibration<HW>:DATA:UPDate:LEVel:FORCe
```

class ForceCls

Force commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: CALibration<HW>:DATA:UPDate:LEVel:FORCe
driver.calibration.data.update.level.force.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: CALibration<HW>:DATA:UPDate:LEVel:FORCe
driver.calibration.data.update.level.force.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.1.3 Delay

SCPI Commands :

```
CALibration:DElay:MINutes
CALibration:DElay:[MEASure]
```

class DelayCls

Delay commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_measure() → bool

```
# SCPI: CALibration:DElay:[MEASure]
value: bool = driver.calibration.delay.get_measure()
```

No command help available

```
return
    error: No help available
```

get_minutes() → int

```
# SCPI: CALibration:DElay:MINutes
value: int = driver.calibration.delay.get_minutes()
```

No command help available

```
return
    minutes: No help available
```

set_minutes(minutes: int) → None

```
# SCPI: CALibration:DElay:MINutes
driver.calibration.delay.set_minutes(minutes = 1)
```

No command help available

```
param minutes
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.delay.clone()
```

Subgroups

6.1.3.1 Shutdown

SCPI Command :

CALibration:DElay:SHUTdown:[STATe]

class ShutdownCls

Shutdown commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: CALibration:DElay:SHUTdown:[STATe]
value: bool = driver.calibration.delay.shutdown.get_state()
```

No command help available

return
shutdown: No help available

set_state(shutdown: bool) → None

```
# SCPI: CALibration:DElay:SHUTdown:[STATe]
driver.calibration.delay.shutdown.set_state(shutdown = False)
```

No command help available

param shutdown
No help available

6.1.4 Frequency

SCPI Command :

CALibration:FREquency:SWPoints

class FrequencyCls

Frequency commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_sw_points() → str

```
# SCPI: CALibration:FREquency:SWPoints
value: str = driver.calibration.frequency.get_sw_points()
```

No command help available

return
freq_switch_point: No help available

set_sw_points(freq_switch_point: str) → None

```
# SCPI: CALibration:FREquency:SWPoints
driver.calibration.frequency.set_sw_points(freq_switch_point = 'abc')
```

No command help available

param freq_switch_point

No help available

6.1.5 Level

SCPI Command :

CALibration<HW>:LEVel:STATe

class LevelCls

Level commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_state() → StateExtended

```
# SCPI: CALibration<HW>:LEVel:STATe
value: enums.StateExtended = driver.calibration.level.get_state()
```

No command help available

return

areg_cal_pow_ext_us: No help available

set_state(areg_cal_pow_ext_us: StateExtended) → None

```
# SCPI: CALibration<HW>:LEVel:STATe
driver.calibration.level.set_state(areg_cal_pow_ext_us = enums.StateExtended.
↳DEFAULT)
```

No command help available

param areg_cal_pow_ext_us

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.level.clone()
```

Subgroups

6.1.5.1 Attenuator

SCPI Command :

CALibration<HW>:LEVel:ATTenuator:STAGe

class AttenuatorCls

Attenuator commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_stage() → int

```
# SCPI: CALibration<HW>:LEVel:ATTenuator:STAGe
value: int = driver.calibration.level.attenuator.get_stage()
```

No command help available

return
stage: No help available

set_stage(stage: int) → None

```
# SCPI: CALibration<HW>:LEVel:ATTenuator:STAGe
driver.calibration.level.attenuator.set_stage(stage = 1)
```

No command help available

param stage
No help available

6.1.6 Roscillator

class RoscillatorCls

Roscillator commands group definition. 3 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.roscillator.clone()
```

Subgroups

6.1.6.1 Data

SCPI Commands :

```
CALibration:ROSCillator:DATA:MODE
CALibration:ROSCillator:[DATA]
```

class DataCls

Data commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_mode() → CalDataMode

```
# SCPI: CALibration:ROSCillator:DATA:MODE
value: enums.CalDataMode = driver.calibration.roscillator.data.get_mode()
```

No command help available

return
mode: No help available

get_value() → int

```
# SCPI: CALibration:ROSCillator:[DATA]
value: int = driver.calibration.roscillator.data.get_value()
```

No command help available

return
data: No help available

set_mode(mode: CalDataMode) → None

```
# SCPI: CALibration:ROSCillator:DATA:MODE
driver.calibration.roscillator.data.set_mode(mode = enums.CalDataMode.CUSTOMER)
```

No command help available

param mode
No help available

set_value(data: int) → None

```
# SCPI: CALibration:ROSCillator:[DATA]
driver.calibration.roscillator.data.set_value(data = 1)
```

No command help available

param data
No help available

6.1.6.2 Store

SCPI Command :

```
CALibration:ROSCillator:STORE
```

class StoreCls

Store commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: CALibration:ROSCillator:STORE
driver.calibration.roscillator.store.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: CALibration:ROSCillator:STORE
driver.calibration.roscillator.store.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms
Maximum time to wait in milliseconds, valid only for this call.

6.1.7 Selected

class SelectedCls

Selected commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.calibration.selected.clone()
```

Subgroups

6.1.7.1 Measure

SCPI Command :

```
CALibration:SElected:[MEASure]
```

class MeasureCls

Measure commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(to_test_args: str) → TestCalSelected

```
# SCPI: CALibration:SElected:[MEASure]
value: enums.TestCalSelected = driver.calibration.selected.measure.get(to_test_
↪args = 'abc')
```

No command help available

param to_test_args
No help available

return
test_result: No help available

6.1.8 Tselected

SCPI Commands :

```
CALibration:TSElected:CATalog
CALibration:TSElected:STEP
CALibration:TSElected:[MEASure]
```

class TselectedCls

Tselected commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_catalog() → str

```
# SCPI: CALibration:TSElected:CATalog
value: str = driver.calibration.tselected.get_catalog()
```


No command help available

```

return
    catalog: No help available

```

get_measure() → bool

```

# SCPI: CALibration:TSElected:[MEASure]
value: bool = driver.calibration.tselected.get_measure()

```

No command help available

```

return
    meas: No help available

```

get_step() → str

```

# SCPI: CALibration:TSElected:STEP
value: str = driver.calibration.tselected.get_step()

```

No command help available

```

return
    sel_string: No help available

```

set_step(sel_string: str) → None

```

# SCPI: CALibration:TSElected:STEP
driver.calibration.tselected.set_step(sel_string = 'abc')

```

No command help available

```

param sel_string
    No help available

```

6.2 Device

SCPI Command :

DEvice:PRESet

class DeviceCls

Device commands group definition. 3 total commands, 1 Subgroups, 1 group commands

preset() → None

```

# SCPI: DEvice:PRESet
driver.device.preset()

```

Presets all parameters which are not related to the signal path, including the LF generator.

preset_with_opc(opc_timeout_ms: int = -1) → None

```

# SCPI: DEvice:PRESet
driver.device.preset_with_opc()

```

Presets all parameters which are not related to the signal path, including the LF generator.

Same as preset, but waits for the operation to complete before continuing further. Use the `RsAreg.utilities.opc_timeout_set()` to set the timeout value.

param `opc_timeout_ms`

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.device.clone()
```

Subgroups

6.2.1 Settings

class `SettingsCls`

Settings commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.device.settings.clone()
```

Subgroups

6.2.1.1 Backup

SCPI Command :

```
DEvice:SETTings:BACKup
```

class `BackupCls`

Backup commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: DEvice:SETTings:BACKup
driver.device.settings.backup.set()
```

No command help available

set_with_opc(*opc_timeout_ms: int = -1*) → None

```
# SCPI: DEvice:SETTings:BACKup
driver.device.settings.backup.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.2.1.2 Restore

SCPI Command :

```
DEVIce:SETTIngs:REStore
```

class RestoreCls

Restore commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: DEVIce:SETTIngs:REStore
driver.device.settings.restore.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: DEVIce:SETTIngs:REStore
driver.device.settings.restore.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.3 Diagnostic

class DiagnosticCls

Diagnostic commands group definition. 17 total commands, 7 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.clone()
```

Subgroups

6.3.1 BgInfo

SCPI Commands :

```
DIAGnostic<HW>:BGInfo
DIAGnostic<HW>:BGInfo:CATalog
```

class BgInfoCls

BgInfo commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get(board: str = None) → str

```
# SCPI: DIAGnostic<HW>:BGInfo
value: str = driver.diagnostic.bgInfo.get(board = 'abc')
```

Queries information on the modules available in the instrument, using the variant and revision state.

param board

string Module name, as queried with the command method RsAreg.Diagnostic.BgInfo.catalog. To retrieve a complete list of all modules, omit the parameter. The length of the list is variable and depends on the instrument equipment configuration.

return

bg_info: Module name Module stock number incl. variant Module revision Module serial number List of comma-separated entries, one entry per module. Each entry for one module consists of four parts that are separated by space characters.

get_catalog() → List[str]

```
# SCPI: DIAGnostic<HW>:BGInfo:CATalog
value: List[str] = driver.diagnostic.bgInfo.get_catalog()
```

Queries the names of the assemblies available in the instrument.

return

catalog: string List of all assemblies; the values are separated by commas The length of the list is variable and depends on the instrument equipment configuration.

6.3.2 Debug

class DebugCls

Debug commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.debug.clone()
```

Subgroups

6.3.2.1 Page

SCPI Commands :

```
DIAGnostic<HW>:DEBug:PAGE
DIAGnostic<HW>:DEBug:PAGE:CATalog
```

class PageCls

Page commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: DIAGnostic<HW>:DEBug:PAGE:CATalog
value: List[str] = driver.diagnostic.debug.page.get_catalog()
```

No command help available

```
return
diag_debug_page_id_cat: No help available
```

set() → None

```
# SCPI: DIAGnostic<HW>:DEBug:PAGE
driver.diagnostic.debug.page.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: DIAGnostic<HW>:DEBug:PAGE
driver.diagnostic.debug.page.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

```
param opc_timeout_ms
Maximum time to wait in milliseconds, valid only for this call.
```

6.3.3 Eeprom<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.diagnostic.eeprom.repcap_channel_get()
driver.diagnostic.eeprom.repcap_channel_set(repcap.Channel.Nr1)
```

SCPI Command :

```
DIAGnostic<HW>:EEPROM<CH>:DElete
```

class EepromCls

Eeprom commands group definition. 4 total commands, 3 Subgroups, 1 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

delete(channel=Channel.Default) → None

```
# SCPI: DIAGnostic<HW>:EEPROM<CH>:DElete
driver.diagnostic.eeprom.delete(channel = repcap.Channel.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Eeprom')

delete_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.eeprom.clone()
```

Subgroups

6.3.3.1 Bidentifier

class BidentifierCls

Bidentifier commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.eeprom.bidentifier.clone()
```

Subgroups

6.3.3.1.1 Catalog

SCPI Command :

```
DIAGnostic<HW>:EEPROM<CH>:BIDentifier:CATalog
```

class CatalogCls

Catalog commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(board_id: List[str], channel=Channel.Default) → List[str]

```
# SCPI: DIAGnostic<HW>:EEPROM<CH>:BIDentifier:CATalog
value: List[str] = driver.diagnostic.eeprom.bidentifier.catalog.get(board_id = [
    ↪ 'abc1', 'abc2', 'abc3'], channel = repcap.Channel.Default)
```

No command help available

param board_id

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Eeprom')

return

board_id: No help available

6.3.3.2 Customize

SCPI Command :

```
DIAGnostic<HW>:EEPROM<CH>:CUSTomize
```

class CustomizeCls

Customize commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(board: str, index: int, sub_board: int, channel=Channel.Default) → None

```
# SCPI: DIAGnostic<HW>:EEPROM<CH>:CUSTomize
driver.diagnostic.eeprom.customize.set(board = 'abc', index = 1, sub_board = 1,
    ↪ channel = repcap.Channel.Default)
```

No command help available

param board

No help available

param index

No help available

param sub_board

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Eeprom')

6.3.3.3 Data

class DataCls

Data commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.eeprom.data.clone()
```

Subgroups

6.3.3.3.1 Points

SCPI Command :

```
DIAGnostic<HW>:EEPROM<CH>:DATA:POINTS
```

class PointsCls

Points commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(board: str, sub_board: str, channel=Channel.Default) → int

```
# SCPI: DIAGnostic<HW>:EEPROM<CH>:DATA:POINTS
value: int = driver.diagnostic.eeprom.data.points.get(board = 'abc', sub_board_
↳= 'abc', channel = repcap.Channel.Default)
```

No command help available

param board

No help available

param sub_board

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Eeprom')

return

points: No help available

6.3.4 Info

class InfoCls

Info commands group definition. 4 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.info.clone()
```

Subgroups

6.3.4.1 Otime

SCPI Commands :

```
DIAGnostic:INFO:OTIME:SET
DIAGnostic:INFO:OTIME
```

class OtimeCls

Otime commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_set() → int

```
# SCPI: DIAGnostic:INFO:OTIME:SET
value: int = driver.diagnostic.info.otime.get_set()
```

No command help available

```
return
    set_py: No help available
```

get_value() → int

```
# SCPI: DIAGnostic:INFO:OTIME
value: int = driver.diagnostic.info.otime.get_value()
```

Queries the operating hours of the instrument so far.

```
return
    operation_time: integer Range: 0 to INT_MAX
```

set_set(set_py: int) → None

```
# SCPI: DIAGnostic:INFO:OTIME:SET
driver.diagnostic.info.otime.set_set(set_py = 1)
```

No command help available

```
param set_py
    No help available
```

6.3.4.2 PoCount

SCPI Commands :

```
DIAGnostic:INFO:POCount:SET  
DIAGnostic:INFO:POCount
```

class PoCountCls

PoCount commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_set() → int

```
# SCPI: DIAGnostic:INFO:POCount:SET  
value: int = driver.diagnostic.info.poCount.get_set()
```

No command help available

```
return  
    set_py: No help available
```

get_value() → int

```
# SCPI: DIAGnostic:INFO:POCount  
value: int = driver.diagnostic.info.poCount.get_value()
```

Queris how often the instrument has been turned on so far.

```
return  
    power_on_count: integer Range: 0 to INT_MAX
```

set_set(set_py: int) → None

```
# SCPI: DIAGnostic:INFO:POCount:SET  
driver.diagnostic.info.poCount.set_set(set_py = 1)
```

No command help available

```
param set_py  
    No help available
```

6.3.5 Measure

class MeasureCls

Measure commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.measure.clone()
```

Subgroups

6.3.5.1 Point

SCPI Command :

```
DIAGnostic<HW>:[MEASure]:POINT
```

class PointCls

Point commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(name: str) → str

```
# SCPI: DIAGnostic<HW>:[MEASure]:POINT
value: str = driver.diagnostic.measure.point.get(name = 'abc')
```

Triggers the voltage measurement at the specified test point and returns the measured voltage. For more information, see R&S AREG100A Service Manual.

param name

test point identifier Test point name, as queried with the command method
RsAreg.Diagnostic.Point.catalog

return

value: valueunit

6.3.6 Point

SCPI Command :

```
DIAGnostic<HW>:POINT:CATalog
```

class PointCls

Point commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_catalog() → List[str]

```
# SCPI: DIAGnostic<HW>:POINT:CATalog
value: List[str] = driver.diagnostic.point.get_catalog()
```

Queries the test points available in the instrument. For more information, see R&S AREG100A Service Manual.

return

catalog: string List of comma-separated values, each representing a test point

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.diagnostic.point.clone()
```

Subgroups

6.3.6.1 Configuration

SCPI Command :

```
DIAGnostic<HW>:POINT:CONFiguration
```

class ConfigurationCls

Configuration commands group definition. 1 total commands, 0 Subgroups, 1 group commands

class GetStruct

Response structure. Fields:

- Dev_Board: str: No parameter help available
- Point: str: No parameter help available

get() → GetStruct

```
# SCPI: DIAGnostic<HW>:POINT:CONFiguration
value: GetStruct = driver.diagnostic.point.configuration.get()
```

No command help available

return

structure: for return value, see the help for GetStruct structure arguments.

set(dev_board: str, point: str, data: str) → None

```
# SCPI: DIAGnostic<HW>:POINT:CONFiguration
driver.diagnostic.point.configuration.set(dev_board = 'abc', point = 'abc',
↳data = 'abc')
```

No command help available

param dev_board

No help available

param point

No help available

param data

No help available

6.3.7 Service

SCPI Commands :

```
DIAGnostic<HW>:Service:SFunction
DIAGnostic:Service
```

class ServiceCls

Service commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_sfunction() → str

```
# SCPI: DIAGnostic<HW>:Service:SFunction
value: str = driver.diagnostic.service.get_sfunction()
```

No command help available

```
return
    direct_string: No help available
```

get_value() → bool

```
# SCPI: DIAGnostic:Service
value: bool = driver.diagnostic.service.get_value()
```

No command help available

```
return
    service: No help available
```

set_sfunction(direct_string: str) → None

```
# SCPI: DIAGnostic<HW>:Service:SFunction
driver.diagnostic.service.set_sfunction(direct_string = 'abc')
```

No command help available

```
param direct_string
    No help available
```

set_value(service: bool) → None

```
# SCPI: DIAGnostic:Service
driver.diagnostic.service.set_value(service = False)
```

No command help available

```
param service
    No help available
```

6.4 Display

SCPI Commands :

```
DISPlay:BRIGhtness
DISPlay:FOCusobject
DISPlay:MESSage
```

class DisplayCls

Display commands group definition. 19 total commands, 7 Subgroups, 3 group commands

get_brightness() → float

```
# SCPI: DISPlay:BRIGhtness
value: float = driver.display.get_brightness()
```

Sets the brightness of the dispaly.

return
brightness: float Range: 1.0 to 20.0

set_brightness(brightness: float) → None

```
# SCPI: DISPlay:BRIGhtness
driver.display.set_brightness(brightness = 1.0)
```

Sets the brightness of the dispaly.

param brightness
float Range: 1.0 to 20.0

set_focus_object(obj_name: str) → None

```
# SCPI: DISPlay:FOCusobject
driver.display.set_focus_object(obj_name = 'abc')
```

No command help available

param obj_name
No help available

set_message(message: str) → None

```
# SCPI: DISPlay:MESSage
driver.display.set_message(message = 'abc')
```

No command help available

param message
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.display.clone()
```

Subgroups

6.4.1 Annotation

SCPI Command :

```
DISPlay:ANNotation:[ALL]
```

class AnnotationCls

Annotation commands group definition. 3 total commands, 2 Subgroups, 1 group commands

get_all() → bool

```
# SCPI: DISPlay:ANNotation:[ALL]
value: bool = driver.display.annotation.get_all()
```

Displays asterisks instead of the level and frequency values in the status bar of the instrument. We recommend that you use this mode if you operate the instrument in remote control.

```
return
state: 0| 1| OFF| ON
```

set_all(state: bool) → None

```
# SCPI: DISPlay:ANNotation:[ALL]
driver.display.annotation.set_all(state = False)
```

Displays asterisks instead of the level and frequency values in the status bar of the instrument. We recommend that you use this mode if you operate the instrument in remote control.

```
param state
0| 1| OFF| ON
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.display.annotation.clone()
```

Subgroups

6.4.1.1 Amplitude

SCPI Command :

DISPlay:ANNotation:AMPLitude

class AmplitudeCls

Amplitude commands group definition. 1 total commands, 0 Subgroups, 1 group commands

class AmplitudeStruct

Response structure. Fields:

- Sec_Pass_Word: str: No parameter help available
- State: bool: 0| 1| OFF| ON

get() → AmplitudeStruct

```
# SCPI: DISPlay:ANNotation:AMPLitude
value: AmplitudeStruct = driver.display.annotation.amplitude.get()
```

Indicates asterisks instead of the level values in the status bar.

return

structure: for return value, see the help for AmplitudeStruct structure arguments.

set(*sec_pass_word*: str, *state*: bool) → None

```
# SCPI: DISPlay:ANNotation:AMPLitude
driver.display.annotation.amplitude.set(sec_pass_word = 'abc', state = False)
```

Indicates asterisks instead of the level values in the status bar.

param sec_pass_word

No help available

param state

0| 1| OFF| ON

6.4.1.2 Frequency

SCPI Command :

DISPlay:ANNotation:FREQuency

class FrequencyCls

Frequency commands group definition. 1 total commands, 0 Subgroups, 1 group commands

class FrequencyStruct

Response structure. Fields:

- Sec_Pass_Word: str: No parameter help available
- State: bool: 0| 1| OFF| ON

get() → FrequencyStruct

```
# SCPI: DISPlay:ANNotation:FREquency
value: FrequencyStruct = driver.display.annotation.frequency.get()
```

Indicates asterisks instead of the frequency values in the status bar.

return

structure: for return value, see the help for FrequencyStruct structure arguments.

set(sec_pass_word: str, state: bool) → None

```
# SCPI: DISPlay:ANNotation:FREquency
driver.display.annotation.frequency.set(sec_pass_word = 'abc', state = False)
```

Indicates asterisks instead of the frequency values in the status bar.

param sec_pass_word

No help available

param state

0| 1| OFF| ON

6.4.2 Button

SCPI Command :

```
DISPlay:BUtTon:BRIGhtness
```

class ButtonCls

Button commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_brightness() → int

```
# SCPI: DISPlay:BUtTon:BRIGhtness
value: int = driver.display.button.get_brightness()
```

Sets the brightness of the [RF on/off] key.

return

button_brightnes: integer Range: 1 to 20

set_brightness(button_brightnes: int) → None

```
# SCPI: DISPlay:BUtTon:BRIGhtness
driver.display.button.set_brightness(button_brightnes = 1)
```

Sets the brightness of the [RF on/off] key.

param button_brightnes

integer Range: 1 to 20

6.4.3 Dialog

SCPI Commands :

```
DISPlay:DIALog:CLOSe
DISPlay:DIALog:CLOSe:ALL
DISPlay:DIALog:ID
DISPlay:DIALog:OPEN
```

class DialogCls

Dialog commands group definition. 4 total commands, 0 Subgroups, 4 group commands

close(*dialog_id: str*) → None

```
# SCPI: DISPlay:DIALog:CLOSe
driver.display.dialog.close(dialog_id = 'abc')
```

Closes the specified dialog.

param dialog_id

string To find out the dialog identifier, use the query method RsAreg.Display.Dialog.id.
The DialogName part of the query result is sufficient.

close_all() → None

```
# SCPI: DISPlay:DIALog:CLOSe:ALL
driver.display.dialog.close_all()
```

Closes all open dialogs.

close_all_with_opc(*opc_timeout_ms: int = -1*) → None

```
# SCPI: DISPlay:DIALog:CLOSe:ALL
driver.display.dialog.close_all_with_opc()
```

Closes all open dialogs.

Same as close_all, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_id() → str

```
# SCPI: DISPlay:DIALog:ID
value: str = driver.display.dialog.get_id()
```

Returns the dialog identifiers of the open dialogs in a string separated by blanks.

return

dialog_id_list: DialogID#1 DialogID#2 ... DialogID#n Dialog identifiers are string without blanks. Blanks are represented as \$. Dialog identifiers DialogID are composed of two main parts: DialogName[OptionalParts] Dialog-Name Meaningful information, mandatory input parameter for the commands: method RsAreg.Display.Dialog.open method RsAreg.Display.Dialog.close Optional

parts String of \$X values, where X is a character, interpreted as follows: \$qDialogQualifier: optional dialog qualifier, usually the letter A or B, as displayed in the dialog title. \$iInstances: comma-separated list of instance indexes, given in the order h,c,s,d,g,u,0. Default is zero; the terminating '0' can be omitted. \$tTabIds: comma-separated indexes or tab names; required, if a dialog is composed of several tabs. \$xLeft\$yTop\$hLeft\$wTop: position and size; superfluous information.

open(dialog_id: str) → None

```
# SCPI: DISPlay:DIALog:OPEN
driver.display.dialog.open(dialog_id = 'abc')
```

Opens the specified dialog.

param dialog_id

string To find out the dialog identifier, use the query method RsAreg.Display.Dialog.id. The DialogName part of the query result is mandatory.

6.4.4 Psave

SCPI Commands :

```
DISPlay:PSAVe:HOLDoff
DISPlay:PSAVe:[STATe]
```

class PsaveCls

Psave commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_holdoff() → int

```
# SCPI: DISPlay:PSAVe:HOLDoff
value: int = driver.display.psave.get_holdoff()
```

Sets the wait time for the screen saver mode of the display.

return

holdoff_time_min: integer Range: 1 to 60, Unit: minute

get_state() → bool

```
# SCPI: DISPlay:PSAVe:[STATe]
value: bool = driver.display.psave.get_state()
```

Activates the screen saver mode of the display. We recommend that you use this mode to protect the display, if you operate the instrument in remote control. To define the wait time, use the command method RsAreg.Display.Psave.holdoff.

return

state: 0| 1| OFF| ON

set_holdoff(holdoff_time_min: int) → None

```
# SCPI: DISPlay:PSAVe:HOLDoff
driver.display.psave.set_holdoff(holdoff_time_min = 1)
```

Sets the wait time for the screen saver mode of the display.

param holdoff_time_min
integer Range: 1 to 60, Unit: minute

set_state(state: bool) → None

```
# SCPI: DISPlay:PSAVe:[STATE]
driver.display.psave.set_state(state = False)
```

Activates the screen saver mode of the display. We recommend that you use this mode to protect the display, if you operate the instrument in remote control. To define the wait time, use the command method RsAreg.Display.Psave.holdoff.

param state
0| 1| OFF| ON

6.4.5 Touch

class TouchCls

Touch commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.display.touch.clone()
```

Subgroups

6.4.5.1 Time

SCPI Command :

```
DISPlay:TOUCh:TIME:CHARge
```

class TimeCls

Time commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set_charge(charge_time: int) → None

```
# SCPI: DISPlay:TOUCh:TIME:CHARge
driver.display.touch.time.set_charge(charge_time = 1)
```

No command help available

param charge_time
No help available

6.4.6 Ukey

SCPI Commands :

```
DISPlay:UKEY:NAME
DISPlay:UKEY:SCPI
```

class UkeyCls

Ukey commands group definition. 3 total commands, 1 Subgroups, 2 group commands

set_name(name: str) → None

```
# SCPI: DISPlay:UKEY:NAME
driver.display.ukey.set_name(name = 'abc')
```

No command help available

param name

No help available

set_scpi(scpi: str) → None

```
# SCPI: DISPlay:UKEY:SCPI
driver.display.ukey.set_scpi(scpi = 'abc')
```

No command help available

param scpi

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.display.ukey.clone()
```

Subgroups

6.4.6.1 Add

SCPI Command :

```
DISPlay:UKEY:ADD
```

class AddCls

Add commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: DISPlay:UKEY:ADD
driver.display.ukey.add.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: DISPlay:UKEY:ADD
driver.display.ukey.add.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.4.7 Update

SCPI Commands :

```
DISPlay:UPDate:HOLD
DISPlay:UPDate:[STATe]
```

class UpdateCls

Update commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_hold() → bool

```
# SCPI: DISPlay:UPDate:HOLD
value: bool = driver.display.update.get_hold()
```

No command help available

return

hold: No help available

get_state() → bool

```
# SCPI: DISPlay:UPDate:[STATe]
value: bool = driver.display.update.get_state()
```

Activates the refresh mode of the display.

return

update: 0| 1| OFF| ON

set_hold(hold: bool) → None

```
# SCPI: DISPlay:UPDate:HOLD
driver.display.update.set_hold(hold = False)
```

No command help available

param hold

No help available

set_state(update: bool) → None

```
# SCPI: DISPlay:UPDate:[STATe]
driver.display.update.set_state(update = False)
```

Activates the refresh mode of the display.

param update
0| 1| OFF| ON

6.5 FormatPy

SCPI Commands :

```
FORMat:BORDER
FORMat:SREGister
FORMat:[DATA]
```

class FormatPyCls

FormatPy commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_border() → ByteOrder

```
# SCPI: FORMat:BORDER
value: enums.ByteOrder = driver.formatPy.get_border()
```

Determines the sequence of bytes within a binary block. This only affects blocks which use the IEEE754 format internally.

return
border: NORMal| SWAPped NORMal Expects/sends the least significant byte of each IEEE754 floating-point number first and the most significant byte last. SWAPped Expects/sends the most significant byte of each IEEE754 floating-point number first and the least significant byte last.

get_data() → FormData

```
# SCPI: FORMat:[DATA]
value: enums.FormData = driver.formatPy.get_data()
```

Determines the data format the instrument uses to return data via the IEC/IEEE bus. The instrument automatically detects the data format used by the controller, and assigns it accordingly. Data format determined by this SCPI command is in this case irrelevant.

return
data: ASCii| PACKed ASCii Transfers numerical data as plain text separated by commas. PACKed Transfers numerical data as binary block data. The format within the binary data depends on the command. The various binary data formats are explained in the description of the parameter types.

get_sregister() → FormStatReg

```
# SCPI: FORMat:SREGister
value: enums.FormStatReg = driver.formatPy.get_sregister()
```

Determines the numeric format for responses of the status register.

return

`format_py`: ASCII| BINARY| HEXadecimal| OCTal ASCII Returns the register content as a decimal number. BINARY|HEXadecimal|OCTal Returns the register content either as a binary, hexadecimal or octal number. According to the selected format, the number starts with #B (binary) , #H (hexadecimal) or #O (octal) .

set_border(*border: ByteOrder*) → None

```
# SCPI: FORMat:BORDER
driver.formatPy.set_border(border = enums.ByteOrder.NORMAL)
```

Determines the sequence of bytes within a binary block. This only affects blocks which use the IEEE754 format internally.

param border

NORMAL| SWAPped NORMAL Expects/sends the least significant byte of each IEEE754 floating-point number first and the most significant byte last. SWAPped Expects/sends the most significant byte of each IEEE754 floating-point number first and the least significant byte last.

set_data(*data: FormData*) → None

```
# SCPI: FORMat:[DATA]
driver.formatPy.set_data(data = enums.FormData.ASCII)
```

Determines the data format the instrument uses to return data via the IEC/IEEE bus. The instrument automatically detects the data format used by the controller, and assigns it accordingly. Data format determined by this SCPI command is in this case irrelevant.

param data

ASCII| PACKed ASCII Transfers numerical data as plain text separated by commas. PACKed Transfers numerical data as binary block data. The format within the binary data depends on the command. The various binary data formats are explained in the description of the parameter types.

set_sregister(*format_py: FormStatReg*) → None

```
# SCPI: FORMat:SREGister
driver.formatPy.set_sregister(format_py = enums.FormStatReg.ASCII)
```

Determines the numeric format for responses of the status register.

param format_py

ASCII| BINARY| HEXadecimal| OCTal ASCII Returns the register content as a decimal number. BINARY|HEXadecimal|OCTal Returns the register content either as a binary, hexadecimal or octal number. According to the selected format, the number starts with #B (binary) , #H (hexadecimal) or #O (octal) .

6.6 Fpanel

class FpanelCls

Fpanel commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.fpanel.clone()
```

Subgroups

6.6.1 Keyboard

SCPI Command :

```
FPANel:KEYBoard:LAYout
```

class KeyboardCls

Keyboard commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_layout() → FrontPanelLayout

```
# SCPI: FPANel:KEYBoard:LAYout
value: enums.FrontPanelLayout = driver.fpanel.keyboard.get_layout()
```

No command help available

return
layout: No help available

set_layout(layout: FrontPanelLayout) → None

```
# SCPI: FPANel:KEYBoard:LAYout
driver.fpanel.keyboard.set_layout(layout = enums.FrontPanelLayout.DIGits)
```

No command help available

param layout
No help available

6.7 HardCopy

SCPI Commands :

```
HCOPy:DATA
HCOPy:REGion
```

class HardCopyCls

HardCopy commands group definition. 17 total commands, 4 Subgroups, 2 group commands

get_data() → bytes

```
# SCPI: HCOpy:DATA
value: bytes = driver.hardCopy.get_data()
```

Transfers the hard copy data directly as a NByte stream to the remote client.

return
data: block data

get_region() → HardCopyRegion

```
# SCPI: HCOpy:REgion
value: enums.HardCopyRegion = driver.hardCopy.get_region()
```

Selects the area to be copied. You can create a snapshot of the screen or an active dialog.

return
region: ALL|DIALOG

set_region(region: HardCopyRegion) → None

```
# SCPI: HCOpy:REgion
driver.hardCopy.set_region(region = enums.HardCopyRegion.ALL)
```

Selects the area to be copied. You can create a snapshot of the screen or an active dialog.

param region
ALL|DIALOG

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.clone()
```

Subgroups**6.7.1 Device****SCPI Command :**

```
HCOPy:DEvice:LANGuage
```

class DeviceCls

Device commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_language() → HardCopyImageFormat

```
# SCPI: HCOpy:DEvice:LANGuage
value: enums.HardCopyImageFormat = driver.hardCopy.device.get_language()
```

Selects the graphic format for the hard copy. You can use both commands alternatively.

return
language: BMP| JPG| XPM| PNG

set_language(*language: HardCopyImageFormat*) → None

```
# SCPI: HCOpy:DEvice:LANGuage
driver.hardCopy.device.set_language(language = enums.HardCopyImageFormat.BMP)
```

Selects the graphic format for the hard copy. You can use both commands alternatively.

param language
BMP| JPG| XPM| PNG

6.7.2 Execute

SCPI Command :

HCOpy:[EXECute]

class ExecuteCls

Execute commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: HCOpy:[EXECute]
driver.hardCopy.execute.set()
```

Generates a hard copy of the current display. The output destination is a file.

set_with_opc(*opc_timeout_ms: int = -1*) → None

```
# SCPI: HCOpy:[EXECute]
driver.hardCopy.execute.set_with_opc()
```

Generates a hard copy of the current display. The output destination is a file.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms
Maximum time to wait in milliseconds, valid only for this call.

6.7.3 File

class FileCls

File commands group definition. 12 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.file.clone()
```

Subgroups

6.7.3.1 Name

SCPI Command :

```
HCOPY:FILE:[NAME]
```

class NameCls

Name commands group definition. 12 total commands, 1 Subgroups, 1 group commands

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]
value: str = driver.hardCopy.file.name.get_value()
```

Determines the file name and path to save the hard copy, provided automatic naming is disabled. Note: If you have enabled automatic naming, the instrument automatically generates the file name and directory, see 'Automatic Naming'.

return
name: string

set_value(name: str) → None

```
# SCPI: HCOpy:FILE:[NAME]
driver.hardCopy.file.name.set_value(name = 'abc')
```

Determines the file name and path to save the hard copy, provided automatic naming is disabled. Note: If you have enabled automatic naming, the instrument automatically generates the file name and directory, see 'Automatic Naming'.

param name
string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.file.name.clone()
```

Subgroups

6.7.3.1.1 Auto

SCPI Commands :

```
HCOPY:FILE:[NAME]:AUTO:STATE
HCOPY:FILE:[NAME]:AUTO
```

class AutoCls

Auto commands group definition. 11 total commands, 2 Subgroups, 2 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:STATE
value: bool = driver.hardCopy.file.name.auto.get_state()
```

Activates automatic naming of the hard copy files.

```
return
state: 0| 1| OFF| ON
```

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]:AUTO
value: str = driver.hardCopy.file.name.auto.get_value()
```

Queries path and file name of the hardcopy file, if you have enabled Automatic Naming.

```
return
auto: string
```

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:STATE
driver.hardCopy.file.name.auto.set_state(state = False)
```

Activates automatic naming of the hard copy files.

```
param state
0| 1| OFF| ON
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.file.name.auto.clone()
```

Subgroups

6.7.3.1.1.1 Directory

SCPI Commands :

```
HCOPY:FILE:[NAME]:AUTO:DIRectory:CLEar
HCOPY:FILE:[NAME]:AUTO:DIRectory
```

class DirectoryCls

Directory commands group definition. 2 total commands, 0 Subgroups, 2 group commands

clear() → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:DIRectory:CLEar
driver.hardCopy.file.name.auto.directory.clear()
```

Deletes all files with extensions *.bmp, *.jpg, *.png and *.xpm in the directory set for automatic naming.

clear_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:DIRectory:CLEar
driver.hardCopy.file.name.auto.directory.clear_with_opc()
```

Deletes all files with extensions *.bmp, *.jpg, *.png and *.xpm in the directory set for automatic naming.

Same as clear, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:DIRectory
value: str = driver.hardCopy.file.name.auto.directory.get_value()
```

Determines the path to save the hard copy, if you have enabled Automatic Naming. If the directory does not yet exist, the instrument automatically creates a new directory, using the instrument name and /var/user/ by default.

return

directory: string

set_value(directory: str) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:DIRectory
driver.hardCopy.file.name.auto.directory.set_value(directory = 'abc')
```

Determines the path to save the hard copy, if you have enabled Automatic Naming. If the directory does not yet exist, the instrument automatically creates a new directory, using the instrument name and /var/user/ by default.

param directory

string

6.7.3.1.1.2 File

SCPI Commands :

```
HCOPY:FILE:[NAME]:AUTO:[FILE]:NUMBer
HCOPY:FILE:[NAME]:AUTO:FILE
```

class FileCls

File commands group definition. 7 total commands, 4 Subgroups, 2 group commands

get_number() → int

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:NUMBer
value: int = driver.hardCopy.file.name.auto.file.get_number()
```

Queries the number that is used as part of the file name for the next hard copy in automatic mode. At the beginning, the count starts at 0. The R&S AREG100A searches the specified output directory for the highest number in the stored files. It increases this number by one to achieve a unique name for the new file. The resulting auto number is appended to the resulting file name with at least three digits.

return
number: integer Range: 0 to 999999

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:FILE
value: str = driver.hardCopy.file.name.auto.file.get_value()
```

Queries the name of the automatically named hard copy file. An automatically generated file name consists of: <Prefix><YYYY><MM><DD><Number>.<Format>. You can activate each component separately, to individually design the file name.

return
file: string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.hardCopy.file.name.auto.file.clone()
```

Subgroups

6.7.3.1.1.3 Day

SCPI Command :

```
HCOPY:FILE:[NAME]:AUTO:[FILE]:DAY:STATe
```

class DayCls

Day commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:DAY:STATe
value: bool = driver.hardCopy.file.name.auto.file.day.get_state()
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

return
state: 0| 1| OFF| ON

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:DAY:STATe
driver.hardCopy.file.name.auto.file.day.set_state(state = False)
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

param state
0| 1| OFF| ON

6.7.3.1.1.4 Month

SCPI Command :

```
HCOpy:FILE:[NAME]:AUTO:[FILE]:MONTH:STATe
```

class MonthCls

Month commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:MONTH:STATe
value: bool = driver.hardCopy.file.name.auto.file.month.get_state()
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

return
state: 0| 1| OFF| ON

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:MONTH:STATe
driver.hardCopy.file.name.auto.file.month.set_state(state = False)
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

param state
0| 1| OFF| ON

6.7.3.1.1.5 Prefix

SCPI Commands :

```
HCOPY:FILE:[NAME]:AUTO:[FILE]:PREFIX:STATe
HCOPY:FILE:[NAME]:AUTO:[FILE]:PREFIX
```

class PrefixCls

Prefix commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX:STATe
value: bool = driver.hardCopy.file.name.auto.file.prefix.get_state()
```

Uses the prefix for the automatic generation of the file name, provided PREF:STAT is activated.

```
return
state: 0| 1| OFF| ON
```

get_value() → str

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX
value: str = driver.hardCopy.file.name.auto.file.prefix.get_value()
```

Uses the prefix for the automatic generation of the file name, provided PREF:STAT is activated.

```
return
prefix: No help available
```

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX:STATe
driver.hardCopy.file.name.auto.file.prefix.set_state(state = False)
```

Uses the prefix for the automatic generation of the file name, provided PREF:STAT is activated.

```
param state
0| 1| OFF| ON
```

set_value(prefix: str) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFIX
driver.hardCopy.file.name.auto.file.prefix.set_value(prefix = 'abc')
```

Uses the prefix for the automatic generation of the file name, provided PREF:STAT is activated.

```
param prefix
0| 1| OFF| ON
```

6.7.3.1.1.6 Year

SCPI Command :

```
HCOPY:FILE:[NAME]:AUTO:[FILE]:YEAR:STATE
```

class YearCls

Year commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:YEAR:STATE
value: bool = driver.hardCopy.file.name.auto.file.year.get_state()
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

return
state: 0| 1| OFF| ON

set_state(state: bool) → None

```
# SCPI: HCOpy:FILE:[NAME]:AUTO:[FILE]:YEAR:STATE
driver.hardCopy.file.name.auto.file.year.set_state(state = False)
```

Uses the date parameters (year, month or day) for the automatic naming. You can activate each of the date parameters separately.

param state
0| 1| OFF| ON

6.7.4 Image

SCPI Command :

```
HCOPY:IMAGE:FORMAT
```

class ImageCls

Image commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_format_py() → HardCopyImageFormat

```
# SCPI: HCOpy:IMAGE:FORMAT
value: enums.HardCopyImageFormat = driver.hardCopy.image.get_format_py()
```

Selects the graphic format for the hard copy. You can use both commands alternatively.

return
format_py: No help available

set_format_py(format_py: HardCopyImageFormat) → None

```
# SCPI: HCOpy:IMAGE:FORMAT
driver.hardCopy.image.set_format_py(format_py = enums.HardCopyImageFormat.BMP)
```

Selects the graphic format for the hard copy. You can use both commands alternatively.

```
param format_py
      BMP|JPG|XPM|PNG
```

6.8 Initiate<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.initiate.repcap_channel_get()
driver.initiate.repcap_channel_set(repcap.Channel.Nr1)
```

class InitiateCls

Initiate commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.initiate.clone()
```

Subgroups

6.8.1 Power

class PowerCls

Power commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.initiate.power.clone()
```

Subgroups

6.8.1.1 Continuous

SCPI Command :

```
INITiate<HW>:[POWer]:CONTinuous
```

class ContinuousCls

Continuous commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → bool

```
# SCPI: INITiate<HW>:[POWer]:CONTinuous
value: bool = driver.initiate.power.continuous.get(channel = repcap.Channel.
↪Default)
```

Switches the local state of the continuous power measurement by R&S NRP power sensors on and off. Switching off local state enhances the measurement performance during remote control. The remote measurement is triggered with method RsAreg. **Read.Power.get()**. This command also returns the measurement results. The local state is not affected, measurement results can be retrieved with local state on or off.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Initiate')

return

continuous: 0| 1| OFF| ON

set(*continuous: bool, channel=Channel.Default*) → None

```
# SCPI: INITiate<HW>:[POWer]:CONTinuous
driver.initiate.power.continuous.set(continuous = False, channel = repcap.
↪Channel.Default)
```

Switches the local state of the continuous power measurement by R&S NRP power sensors on and off. Switching off local state enhances the measurement performance during remote control. The remote measurement is triggered with method RsAreg. **Read.Power.get()**. This command also returns the measurement results. The local state is not affected, measurement results can be retrieved with local state on or off.

param continuous

0| 1| OFF| ON

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Initiate')

6.9 Kboard

SCPI Command :

KBOard:LAYout

class KboardCls

Kboard commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_layout() → KbLayout

```
# SCPI: KBOard:LAYout
value: enums.KbLayout = driver.kboard.get_layout()
```

Selects the language for an external keyboard and assigns the keys accordingly.

return

layout: CHINese| DANish| DUTCh| DUTBe| ENGLish| ENGUK| FINNish| FRENch| FREBe| FRECa| GERMan| ITALian| JAPanese| KORean| NORWegian| PORTuguese| RUSSian| SPANish| SWEDish| ENGUS

set_layout(*layout: KbLayout*) → None

```
# SCPI: KBOard:LAYout
driver.kboard.set_layout(layout = enums.KbLayout.CHINese)
```

Selects the language for an external keyboard and assigns the keys accordingly.

param layout

CHINese| DANish| DUTCh| DUTBe| ENGLish| ENGUK| FINNish| FRENch| FREBe| FRECa| GERMan| ITALian| JAPanese| KORean| NORWegian| PORTuguese| RUSSian| SPANish| SWEDish| ENGUS

6.10 MassMemory

SCPI Commands :

```
MMEMory:CDIRectory
MMEMory:COPY
MMEMory:DELeTe
MMEMory:DRIVes
MMEMory:MDIRectory
MMEMory:MOVE
MMEMory:MSIS
MMEMory:RDIRectory
MMEMory:RDIRectory:REcursive
```

class MassMemoryCls

MassMemory commands group definition. 15 total commands, 4 Subgroups, 9 group commands

copy(*source_file: str, destination_file: str*) → None

```
# SCPI: MMEMory:COPY
driver.massMemory.copy(source_file = 'abc', destination_file = 'abc')
```

Copies an existing file to a new file. Instead of just a file, this command can also be used to copy a complete directory together with all its files.

param source_file

string String containing the path and file name of the source file

param destination_file

string String containing the path and name of the target file. The path can be relative or absolute. If DestinationFile is not specified, the SourceFile is copied to the current directory, queried with the method RsAreg.MassMemory.currentDirectory command. Note: Existing files with the same name in the destination directory are overwritten without an error message.

delete(*filename: str*) → None

```
# SCPI: MMEemory:DELeTe
driver.massMemory.delete(filename = 'abc')
```

Removes a file from the specified directory.

param filename

string String parameter to specify the name and directory of the file to be removed.

delete_directory(directory: str) → None

```
# SCPI: MMEemory:RDIRectory
driver.massMemory.delete_directory(directory = 'abc')
```

Removes an existing directory from the mass memory storage system. If no directory is specified, the subdirectory with the specified name is deleted in the default directory.

param directory

string String parameter to specify the directory to be deleted.

delete_directory_recursive(directory: str) → None

```
# SCPI: MMEemory:RDIRectory:RECURSive
driver.massMemory.delete_directory_recursive(directory = 'abc')
```

No command help available

param directory

No help available

get_current_directory() → str

```
# SCPI: MMEemory:CDIRectory
value: str = driver.massMemory.get_current_directory()
```

Changes the default directory for mass memory storage. The directory is used for all subsequent MMEM commands if no path is specified with them.

return

directory: directory_name String containing the path to another directory. The path can be relative or absolute. To change to a higher directory, use two dots '..'.

get_drives() → str

```
# SCPI: MMEemory:DRIVes
value: str = driver.massMemory.get_drives()
```

No command help available

return

drive_list: No help available

get_msis() → str

```
# SCPI: MMEemory:MSIS
value: str = driver.massMemory.get_msis()
```

Defines the drive or network resource (in the case of networks) for instruments with windows operating system, using msis (MSIS = Mass Storage Identification String). Note: Instruments with Linux operating system ignore this command, since Linux does not use drive letter assignment.

return

path: No help available

make_directory(*directory: str*) → None

```
# SCPI: MMEemory:MDIRectory
driver.massMemory.make_directory(directory = 'abc')
```

Creates a subdirectory for mass memory storage in the specified directory. If no directory is specified, a subdirectory is created in the default directory. This command can also be used to create a directory tree.

param directory

string String parameter to specify the new directory.

move(*source_file: str, destination_file: str*) → None

```
# SCPI: MMEemory:MOVE
driver.massMemory.move(source_file = 'abc', destination_file = 'abc')
```

Moves an existing file to a new location or, if no path is specified, renames an existing file.

param source_file

string String parameter to specify the name of the file to be moved.

param destination_file

string String parameters to specify the name of the new file.

set_current_directory(*directory: str*) → None

```
# SCPI: MMEemory:CDIRectory
driver.massMemory.set_current_directory(directory = 'abc')
```

Changes the default directory for mass memory storage. The directory is used for all subsequent MMEM commands if no path is specified with them.

param directory

directory_name String containing the path to another directory. The path can be relative or absolute. To change to a higher directory, use two dots '..' .

set_msis(*path: str*) → None

```
# SCPI: MMEemory:MSIS
driver.massMemory.set_msis(path = 'abc')
```

Defines the drive or network resource (in the case of networks) for instruments with windows operating system, using msis (MSIS = Mass Storage Identification String) . Note: Instruments with Linux operating system ignore this command, since Linux does not use drive letter assignment.

param path

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.clone()
```

Subgroups

6.10.1 Catalog

SCPI Command :

```
MMEMory:CATalog
```

class CatalogCls

Catalog commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_value() → str

```
# SCPI: MMEMory:CATalog
value: str = driver.massMemory.catalog.get_value()
```

Returns the content of a particular directory.

return
catalog: No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.catalog.clone()
```

Subgroups

6.10.1.1 Length

SCPI Command :

```
MMEMory:CATalog:LENGth
```

class LengthCls

Length commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(path: str = None) → int

```
# SCPI: MMEMory:CATalog:LENGth
value: int = driver.massMemory.catalog.length.get(path = 'abc')
```

Returns the number of files in the current or in the specified directory.

param path

string String parameter to specify the directory. If the directory is omitted, the command queries the content of the current directory, queried with method RsAreg.MassMemory.currentDirectory command.

return

file_count: integer Number of files.

6.10.2 Dcatalog

SCPI Command :

```
MMEMory:DCATalog
```

class DcatalogCls

Dcatalog commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_value() → str

```
# SCPI: MMEMory:DCATalog
value: str = driver.massMemory.dcatalog.get_value()
```

Returns the subdirectories of a particular directory.

return

dcatalog: No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.dcatalog.clone()
```

Subgroups

6.10.2.1 Length

SCPI Command :

```
MMEMory:DCATalog:LENGth
```

class LengthCls

Length commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(path: str = None) → int

```
# SCPI: MMEMory:DCATalog:LENGth
value: int = driver.massMemory.dcatalog.length.get(path = 'abc')
```

Returns the number of subdirectories in the current or specified directory.

param path

String parameter to specify the directory. If the directory is omitted, the command queries the contents of the current directory, to be queried with method RsAreg.MassMemory.currentDirectory command.

return

directory_count: integer Number of parent and subdirectories.

6.10.3 Load

class LoadCls

Load commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.load.clone()
```

Subgroups

6.10.3.1 State

SCPI Command :

```
MMEMory:LOAD:STATE
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(data_set: int, source_file: str) → None

```
# SCPI: MMEMory:LOAD:STATE
driver.massMemory.load.state.set(data_set = 1, source_file = 'abc')
```

Loads the specified file stored under the specified name in an internal memory. After the file has been loaded, the instrument setting must be activated using an *RCL command.

param data_set

No help available

param source_file

No help available

6.10.4 Store

class StoreCls

Store commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.massMemory.store.clone()
```

Subgroups

6.10.4.1 State

SCPI Command :

```
MMEMory:STORe:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(data_set: int, destination_file: str) → None

```
# SCPI: MMEMory:STORe:STATe
driver.massMemory.store.state.set(data_set = 1, destination_file = 'abc')
```

Stores the current instrument setting in the specified file. The instrument setting must first be stored in an internal memory with the same number using the common command *SAV.

param data_set

No help available

param destination_file

No help available

6.11 Memory

SCPI Command :

```
MEMory:HFRee
```

class MemoryCls

Memory commands group definition. 1 total commands, 0 Subgroups, 1 group commands

class HfreeStruct

Structure for reading output parameters. Fields:

- Total_Phys_Mem_Kb: List[int]: integer Total physical memory.
- Applic_Mem_Kb: int: integer Application memory.
- Heap_Used_Kb: int: integer Used heap memory.

- Heap_Available_Kb: int: integer Available heap memory.

get_hfree() → HfreeStruct

```
# SCPI: MEMory:HFRee
value: HfreeStruct = driver.memory.get_hfree()
```

Returns the used and available memory in Kb.

return

structure: for return value, see the help for HfreeStruct structure arguments.

6.12 Read<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.read.repcap_channel_get()
driver.read.repcap_channel_set(repcap.Channel.Nr1)
```

class ReadCls

Read commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.read.clone()
```

Subgroups

6.12.1 Power

SCPI Command :

```
READ<CH>:[POWer]
```

class PowerCls

Power commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → List[float]

```
# SCPI: READ<CH>:[POWer]
value: List[float] = driver.read.power.get(channel = repcap.Channel.Default)
```

Triggers power measurement and displays the results. Note: This command does not affect the local state, i.e. you can get results with local state on or off. For long measurement times, we recommend that you use an SRQ for command synchronization (MAV bit) .

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Read')

return

power: float or float,float The sensor returns the result in the unit set with command method RsAreg.Sense.Unit.Power.set Certain power sensors, such as the R&S NRP-Z81, return two values, first the value of the average level and - separated by a comma - the peak value.

6.13 Sense<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.sense.repcap_channel_get()
driver.sense.repcap_channel_set(repcap.Channel.Nr1)
```

class SenseCls

Sense commands group definition. 25 total commands, 2 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.clone()
```

Subgroups

6.13.1 Power

class PowerCls

Power commands group definition. 24 total commands, 14 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.clone()
```

Subgroups

6.13.1.1 Aperture

class ApertureCls

Aperture commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.aperture.clone()
```

Subgroups

6.13.1.1.1 Default

class DefaultCls

Default commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.aperture.default.clone()
```

Subgroups

6.13.1.1.1.1 State

SCPI Command :

```
SENSe<CH>:[POWer]:APERture:DEFault:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSe<CH>:[POWer]:APERture:DEFault:STATe
value: bool = driver.sense.power.aperture.default.state.get(channel = repcap.
↳ Channel.Default)
```

Deactivates the default aperture time of the respective sensor. To specify a user-defined value, use the command method RsAreg.Sense.Power.Aperture.Time.set.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

```

    return
        use_def_ap: 0| 1| OFF| ON

set(use_def_ap: bool, channel=Channel.Default) → None

```

```

# SCPI: SENSE<CH>:[POWer]:APERture:DEFault:STATe
driver.sense.power.aperture.default.state.set(use_def_ap = False, channel = ↵
↵repcap.Channel.Default)

```

Deactivates the default aperture time of the respective sensor. To specify a user-defined value, use the command method RsAreg.Sense.Power.Aperture.Time.set.

```

param use_def_ap
    0| 1| OFF| ON

param channel
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Sense')

```

6.13.1.1.2 Time

SCPI Command :

```
SENSe<CH>:[POWer]:APERture:TIME
```

class TimeCls

Time commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get(channel=Channel.Default) → float
```

```

# SCPI: SENSE<CH>:[POWer]:APERture:TIME
value: float = driver.sense.power.aperture.time.get(channel = repcap.Channel.
↵Default)

```

Defines the aperture time (size of the acquisition interval) for the corresponding sensor.

```

param channel
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Sense')

```

```

return
    ap_time: float Range: depends on connected power sensor

```

```
set(ap_time: float, channel=Channel.Default) → None
```

```

# SCPI: SENSE<CH>:[POWer]:APERture:TIME
driver.sense.power.aperture.time.set(ap_time = 1.0, channel = repcap.Channel.
↵Default)

```

Defines the aperture time (size of the acquisition interval) for the corresponding sensor.

```

param ap_time
    float Range: depends on connected power sensor

param channel
    optional repeated capability selector. Default value: Nr1 (settable in the interface
    'Sense')

```

6.13.1.2 Correction

class CorrectionCls

Correction commands group definition. 3 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.correction.clone()
```

Subgroups

6.13.1.2.1 SpDevice

class SpDeviceCls

SpDevice commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.correction.spDevice.clone()
```

Subgroups

6.13.1.2.1.1 ListPy

SCPI Command :

```
SENSe<CH>:[POWer]:CORRection:SPDevice:LIST
```

class ListPyCls

ListPy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → List[str]

```
# SCPI: SENSe<CH>:[POWer]:CORRection:SPDevice:LIST
value: List[str] = driver.sense.power.correction.spDevice.listPy.get(channel =
↳repcap.Channel.Default)
```

Queries the list of the S-parameter data sets that have been loaded to the power sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

list_py: string list

6.13.1.2.1.2 Select

SCPI Command :

```
SENSe<CH>:[POWer]:CORRection:SPDevice:SElect
```

class SelectCls

Select commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSe<CH>:[POWer]:CORRection:SPDevice:SElect
value: float = driver.sense.power.correction.spDevice.select.get(channel = ↵
↵repcap.Channel.Default)
```

Several S-parameter tables can be stored in a sensor. The command selects a loaded data set for S-parameter correction for the corresponding sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

select: float

set(select: float, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:CORRection:SPDevice:SElect
driver.sense.power.correction.spDevice.select.set(select = 1.0, channel = ↵
↵repcap.Channel.Default)
```

Several S-parameter tables can be stored in a sensor. The command selects a loaded data set for S-parameter correction for the corresponding sensor.

param select

float

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.2.1.3 State

SCPI Command :

```
SENSe<CH>:[POWer]:CORRection:SPDevice:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSe<CH>:[POWer]:CORRection:SPDevice:STATe
value: bool = driver.sense.power.correction.spDevice.state.get(channel = repcap.
↵Channel.Default)
```

Activates the use of the S-parameter correction data. Note: If you use power sensors with attenuator, the instrument automatically activates the use of S-parameter data.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

state: 0| 1| OFF| ON

set(state: bool, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:CORRection:SPDevice:STATE
driver.sense.power.correction.spDevice.state.set(state = False, channel =
↳repcap.Channel.Default)
```

Activates the use of the S-parameter correction data. Note: If you use power sensors with attenuator, the instrument automatically activates the use of S-parameter data.

param state

0| 1| OFF| ON

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.3 Direct

SCPI Command :

```
SENSe<CH>:[POWer]:DIReCt
```

class DirectCls

Direct commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(command: str, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:DIReCt
driver.sense.power.direct.set(command = 'abc', channel = repcap.Channel.Default)
```

No command help available

param command

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.4 Display

class DisplayCls

Display commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.display.clone()
```

Subgroups

6.13.1.4.1 Permanent

class PermanentCls

Permanent commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.display.permanent.clone()
```

Subgroups

6.13.1.4.1.1 Priority

SCPI Command :

```
SENSe<CH>:[POWer]:DISPlay:PERManent:PRIority
```

class PriorityCls

Priority commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → PowSensDisplayPriority

```
# SCPI: SENSe<CH>:[POWer]:DISPlay:PERManent:PRIority
value: enums.PowSensDisplayPriority = driver.sense.power.display.permanent.
↳ priority.get(channel = repcap.Channel.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

priority: No help available

set(*priority: PowSensDisplayPriority, channel=Channel.Default*) → None

```
# SCPI: SENSE<CH>:[POWer]:DISPlay:PERManent:PRIority
driver.sense.power.display.permanent.priority.set(priority = enums.
↳ PowSensDisplayPriority.AVERage, channel = repcap.Channel.Default)
```

No command help available

param priority

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.4.1.2 State

SCPI Command :

```
SENSe<CH>:[POWer]:DISPlay:PERManent:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → bool

```
# SCPI: SENSE<CH>:[POWer]:DISPlay:PERManent:STATe
value: bool = driver.sense.power.display.permanent.state.get(channel = repcap.
↳ Channel.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

state: No help available

set(*state: bool, channel=Channel.Default*) → None

```
# SCPI: SENSE<CH>:[POWer]:DISPlay:PERManent:STATe
driver.sense.power.display.permanent.state.set(state = False, channel = repcap.
↳ Channel.Default)
```

No command help available

param state

No help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.5 FilterPy

class FilterPyCls

FilterPy commands group definition. 6 total commands, 4 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.filterPy.clone()
```

Subgroups

6.13.1.5.1 Length

class LengthCls

Length commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.filterPy.length.clone()
```

Subgroups

6.13.1.5.1.1 Auto

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:LENGth:AUTO
```

class AutoCls

Auto commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSe<CH>:[POWer]:FILTer:LENGth:AUTO
value: float = driver.sense.power.filterPy.length.auto.get(channel = repcap.
↳ Channel.Default)
```

Queries the current filter length in filter mode AUTO (method RsAreg.Sense.Power.FilterPy.TypePy.set)

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

auto: float Range: 1 to 65536

6.13.1.5.1.2 User

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:LENGth:[USER]
```

class UserCls

User commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSE<CH>:[POWer]:FILTer:LENGth:[USER]
value: float = driver.sense.power.filterPy.length.user.get(channel = repcap.
↳Channel.Default)
```

Selects the filter length for SENS:POW:FILT:’TYPE USER. As the filter length works as a multiplier for the time window, a constant filter length results in a constant measurement time (see also ‘About the measuring principle, averaging filter, filter length, and achieving stable results’).

INTRO_CMD_HELP: The R&S NRP power sensors provide different resolutions for setting the filter length, depending on the used sensor type:

- Resolution = 1 for R&S NRPxx power sensors
- Resolution = 2n for sensors of the R&S NRP-Zxx family, with n = 1 to 16

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sense’)

return

user: float Range: 1 to 65536

set(user: float, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:LENGth:[USER]
driver.sense.power.filterPy.length.user.set(user = 1.0, channel = repcap.
↳Channel.Default)
```

Selects the filter length for SENS:POW:FILT:’TYPE USER. As the filter length works as a multiplier for the time window, a constant filter length results in a constant measurement time (see also ‘About the measuring principle, averaging filter, filter length, and achieving stable results’).

INTRO_CMD_HELP: The R&S NRP power sensors provide different resolutions for setting the filter length, depending on the used sensor type:

- Resolution = 1 for R&S NRPxx power sensors
- Resolution = 2n for sensors of the R&S NRP-Zxx family, with n = 1 to 16

param user

float Range: 1 to 65536

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Sense’)

6.13.1.5.2 NsRatio

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:NSRatio
```

class NsRatioCls

NsRatio commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSE<CH>:[POWer]:FILTer:NSRatio
value: float = driver.sense.power.filterPy.nsRatio.get(channel = repcap.Channel.
↳Default)
```

Sets an upper limit for the relative noise content in fixed noise filter mode (method RsAreg.Sense.Power.FilterPy.TypePy. set) . This value determines the proportion of intrinsic noise in the measurement results.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

ns_ratio: float Range: 0.001 to 1

set(ns_ratio: float, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:NSRatio
driver.sense.power.filterPy.nsRatio.set(ns_ratio = 1.0, channel = repcap.
↳Channel.Default)
```

Sets an upper limit for the relative noise content in fixed noise filter mode (method RsAreg.Sense.Power.FilterPy.TypePy. set) . This value determines the proportion of intrinsic noise in the measurement results.

param ns_ratio

float Range: 0.001 to 1

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.filterPy.nsRatio.clone()
```

Subgroups

6.13.1.5.2.1 Mtime

SCPI Command :

SENSe<CH>:[POWer]:FILTer:NSRatio:MTIME

class MtimeCls

Mtime commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSe<CH>:[POWer]:FILTer:NSRatio:MTIME
value: float = driver.sense.power.filterPy.nsRatio.mtime.get(channel = repcap.
↳ Channel.Default)
```

Sets an upper limit for the settling time of the auto-averaging filter in the NSRatio mode and thus limits the length of the filter. The filter type is set with command method RsAreg.Sense.Power.FilterPy.TypePy.set.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

mtime: float Range: 1 to 999.99

set(mtime: float, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:FILTer:NSRatio:MTIME
driver.sense.power.filterPy.nsRatio.mtime.set(mtime = 1.0, channel = repcap.
↳ Channel.Default)
```

Sets an upper limit for the settling time of the auto-averaging filter in the NSRatio mode and thus limits the length of the filter. The filter type is set with command method RsAreg.Sense.Power.FilterPy.TypePy.set.

param mtime

float Range: 1 to 999.99

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.5.3 Sonce

SCPI Command :

SENSe<CH>:[POWer]:FILTer:SONCe

class SonceCls

Sonce commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:SONCe
driver.sense.power.filterPy.sonce.set(channel = repcap.Channel.Default)
```

Starts searching the optimum filter length for the current measurement conditions. You can check the result with command SENS1:POW:FILT:LENG:USER? in filter mode USER (method RsAreg.Sense.Power.FilterPy.TypePy.set) .

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

6.13.1.5.4 TypePy

SCPI Command :

```
SENSe<CH>:[POWer]:FILTer:TYPE
```

class TypePyCls

TypePy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → PowSensFiltType

```
# SCPI: SENSE<CH>:[POWer]:FILTer:TYPE
value: enums.PowSensFiltType = driver.sense.power.filterPy.typePy.get(channel =
↳ repcap.Channel.Default)
```

Selects the filter mode. The filter length is the multiplier for the time window and thus directly affects the measurement time.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

type_py: AUTO| USER| NSRatio AUTO Automatically selects the filter length, depending on the measured value. The higher the power, the shorter the filter length, and vice versa. USER Allows you to set the filter length manually. As the filter-length takes effect as a multiplier of the measurement time, you can achieve constant measurement times. NSRatio Selects the filter length (averaging factor) according to the criterion that the intrinsic noise of the sensor (2 standard deviations) does not exceed the specified noise content. You can define the noise content with command method RsAreg.Sense.Power.FilterPy.NsRatio.set. Note: To avoid long settling times when the power is low, you can limit the averaging factor limited with the 'timeout' parameter (method RsAreg.Sense.Power.FilterPy.NsRatio.Mtime.set) .

set(type_py: PowSensFiltType, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:FILTer:TYPE
driver.sense.power.filterPy.typePy.set(type_py = enums.PowSensFiltType.AUTO,
↳ channel = repcap.Channel.Default)
```

Selects the filter mode. The filter length is the multiplier for the time window and thus directly affects the measurement time.

param type_py

AUTO| USER| NSRatio AUTO Automatically selects the filter length, depending on the measured value. The higher the power, the shorter the filter length, and vice versa. USER Allows you to set the filter length manually. As the filter-length takes effect as a multiplier of the measurement time, you can achieve constant measurement times. NSRatio Selects the filter length (averaging factor) according to the criterion that the intrinsic noise of the sensor (2 standard deviations) does not exceed the specified noise content. You can define the noise content with command method RsAreg.Sense.Power.FilterPy.NsRatio.set. Note: To avoid long settling times when the power is low, you can limit the averaging factor limited with the 'timeout' parameter (method RsAreg.Sense.Power.FilterPy.NsRatio.Mtime.set) .

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.6 Frequency

SCPI Command :

```
SENSe<CH>:[POWer]:FREQuency
```

class FrequencyCls

Frequency commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSe<CH>:[POWer]:FREQuency
value: float = driver.sense.power.frequency.get(channel = repcap.Channel.
↳Default)
```

Sets the RF frequency of the signal, if signal source 'USER' is selected (method RsAreg.Sense.Power.Source.set) .

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

frequency: float

set(frequency: float, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:FREQuency
driver.sense.power.frequency.set(frequency = 1.0, channel = repcap.Channel.
↳Default)
```

Sets the RF frequency of the signal, if signal source 'USER' is selected (method RsAreg.Sense.Power.Source.set) .

param frequency

float

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.7 Logging**class LoggingCls**

Logging commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.logging.clone()
```

Subgroups**6.13.1.7.1 State****SCPI Command :**

```
SENSe<CH>:[POWer]:LOGGing:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSe<CH>:[POWer]:LOGGing:STATe
value: bool = driver.sense.power.logging.state.get(channel = repcap.Channel.
↳Default)
```

Activates the recording of the power values, measured by a connected R&S NRP power sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

state: 0| 1| OFF| ON

set(state: bool, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:LOGGing:STATe
driver.sense.power.logging.state.set(state = False, channel = repcap.Channel.
↳Default)
```

Activates the recording of the power values, measured by a connected R&S NRP power sensor.

param state

0| 1| OFF| ON

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.8 Offset**SCPI Command :**

SENSe<CH>:[POWer]:OFFSet

class OffsetCls

Offset commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get(channel=Channel.Default) → float

```
# SCPI: SENSe<CH>:[POWer]:OFFSet
value: float = driver.sense.power.offset.get(channel = repcap.Channel.Default)
```

Sets a level offset which is added to the measured level value after activation with command method RsAreg.Sense.Power. Offset.State.set. The level offset allows, e.g. to consider an attenuator in the signal path.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

offset: float Range: -100.0 to 100.0, Unit: dB

set(offset: float, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:OFFSet
driver.sense.power.offset.set(offset = 1.0, channel = repcap.Channel.Default)
```

Sets a level offset which is added to the measured level value after activation with command method RsAreg.Sense.Power. Offset.State.set. The level offset allows, e.g. to consider an attenuator in the signal path.

param offset

float Range: -100.0 to 100.0, Unit: dB

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.offset.clone()
```

Subgroups

6.13.1.8.1 State

SCPI Command :

```
SENSe<CH>:[POWer]:OFFSet:STATe
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSE<CH>:[POWer]:OFFSet:STATe
value: bool = driver.sense.power.offset.state.get(channel = repcap.Channel.
↳Default)
```

Activates the addition of the level offset to the measured value. The level offset value is set with command method RsAreg.Sense.Power.Offset.set.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

state: 0| 1| OFF| ON

set(state: bool, channel=Channel.Default) → None

```
# SCPI: SENSE<CH>:[POWer]:OFFSet:STATe
driver.sense.power.offset.state.set(state = False, channel = repcap.Channel.
↳Default)
```

Activates the addition of the level offset to the measured value. The level offset value is set with command method RsAreg.Sense.Power.Offset.set.

param state

0| 1| OFF| ON

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.9 Snumber

SCPI Command :

```
SENSe<CH>:[POWer]:SNUMber
```

class SnumberCls

Snumber commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel*=*Channel.Default*) → str

```
# SCPI: SENSE<CH>:[POWer]:SNUMber
value: str = driver.sense.power.snumber.get(channel = repcap.Channel.Default)
```

Queries the serial number of the sensor.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

snumber: string

6.13.1.10 Source

SCPI Command :

```
SENSe<CH>:[POWer]:SOURce
```

class SourceCls

Source commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel*=*Channel.Default*) → ErFpowSensSourceAreg

```
# SCPI: SENSE<CH>:[POWer]:SOURce
value: enums.ErFpowSensSourceAreg = driver.sense.power.source.get(channel =
↳ repcap.Channel.Default)
```

Determines the signal to be measured. Note: When measuring the RF signal, the sensor considers the corresponding correction factor at that frequency, and uses the level setting of the instrument as reference level.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

source: A| USER| RF

set(*source*: *ErFpowSensSourceAreg*, *channel*=*Channel.Default*) → None

```
# SCPI: SENSE<CH>:[POWer]:SOURce
driver.sense.power.source.set(source = enums.ErFpowSensSourceAreg.USER, channel
↳ repcap.Channel.Default)
```

Determines the signal to be measured. Note: When measuring the RF signal, the sensor considers the corresponding correction factor at that frequency, and uses the level setting of the instrument as reference level.

param source

A| USER| RF

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.13.1.11 Status

class StatusCls

Status commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.power.status.clone()
```

Subgroups

6.13.1.11.1 Device

SCPI Command :

```
SENSe<CH>:[POWer]:STATus:[DEVIce]
```

class DeviceCls

Device commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → bool

```
# SCPI: SENSE<CH>:[POWer]:STATus:[DEVIce]
value: bool = driver.sense.power.status.device.get(channel = repcap.Channel.
↳Default)
```

Queries if a sensor is connected to the instrument.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

status: 0| 1| OFF| ON

6.13.1.12 Sversion

SCPI Command :

```
SENSe<CH>:[POWer]:SVERsion
```

class SversionCls

Sversion commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → str

```
# SCPI: SENSE<CH>:[POWer]:SVERsion
value: str = driver.sense.power.sversion.get(channel = repcap.Channel.Default)
```

No command help available

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

sversion: No help available

6.13.1.13 TypePy

SCPI Command :

```
SENSe<CH>:[POWer]:TYPE
```

class TypePyCls

TypePy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → str

```
# SCPI: SENSe<CH>:[POWer]:TYPE
value: str = driver.sense.power.typePy.get(channel = repcap.Channel.Default)
```

Queries the sensor type. The type is automatically detected.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

type_py: string

6.13.1.14 Zero

SCPI Command :

```
SENSe<CH>:[POWer]:ZERO
```

class ZeroCls

Zero commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:[POWer]:ZERO
driver.sense.power.zero.set(channel = repcap.Channel.Default)
```

Performs zeroing of the sensor. Zeroing is required after warm-up, i.e. after connecting the sensor. Note: Switch off or disconnect the RF power source from the sensor before zeroing.

INTRO_CMD_HELP: We recommend that you zero in regular intervals (at least once a day) , if:

- The temperature has varied more than about 5 °C.
- The sensor has been replaced.
- You want to measure very low power.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

set_with_opc(channel=Channel.Default, opc_timeout_ms: int = -1) → None

6.13.2 Unit

class UnitCls

Unit commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.sense.unit.clone()
```

Subgroups

6.13.2.1 Power

SCPI Command :

```
SENSe<CH>:UNIT:[POWer]
```

class PowerCls

Power commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(channel=Channel.Default) → UnitPowSens

```
# SCPI: SENSe<CH>:UNIT:[POWer]
value: enums.UnitPowSens = driver.sense.unit.power.get(channel = repcap.Channel.
↳Default)
```

Selects the unit (Watt, dBm or dBV) of measurement result display, queried with method **RsAreg.Read.Power.get_**.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

return

power: DBM| DBUV| WATT

set(power: UnitPowSens, channel=Channel.Default) → None

```
# SCPI: SENSe<CH>:UNIT:[POWer]
driver.sense.unit.power.set(power = enums.UnitPowSens.DBM, channel = repcap.
↳Channel.Default)
```

Selects the unit (Watt, dBm or dBV) of measurement result display, queried with method **RsAreg.Read.Power.get_**.

param power

DBM| DBUV| WATT

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Sense')

6.14 Slist

SCPI Commands :

```
SLISt:CLEAr:[ALL]
SLISt:[LIST]
```

class SlistCls

Slist commands group definition. 9 total commands, 4 Subgroups, 2 group commands

clear_all() → None

```
# SCPI: SLISt:CLEAr:[ALL]
driver.slist.clear_all()
```

Removes all R&S NRP power sensors from the list.

clear_all_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SLISt:CLEAr:[ALL]
driver.slist.clear_all_with_opc()
```

Removes all R&S NRP power sensors from the list.

Same as clear_all, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_list_py() → List[str]

```
# SCPI: SLISt:[LIST]
value: List[str] = driver.slist.get_list_py()
```

Returns a list of all detected sensors in a comma-separated string.

return

sensor_list: String of comma-separated entries Each entry contains information on the sensor type, serial number and interface. The order of the entries does not correspond to the order the sensors are displayed in the 'NRP Sensor Mapping' dialog.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.clone()
```

Subgroups

6.14.1 Clear

class ClearCls

Clear commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.clear.clone()
```

Subgroups

6.14.1.1 Lan

SCPI Command :

```
SLISt:CLEAr:LAN
```

class LanCls

Lan commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SLISt:CLEAr:LAN
driver.slist.clear.lan.set()
```

Removes all R&S NRP power sensors connected in the LAN from the list.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SLISt:CLEAr:LAN
driver.slist.clear.lan.set_with_opc()
```

Removes all R&S NRP power sensors connected in the LAN from the list.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.14.1.2 Usb

SCPI Command :

SLISt:CLear:USB

class UsbCls

Usb commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SLISt:CLear:USB
driver.slist.clear.usb.set()
```

Removes all R&S NRP power sensors connected over USB from the list.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SLISt:CLear:USB
driver.slist.clear.usb.set_with_opc()
```

Removes all R&S NRP power sensors connected over USB from the list.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.14.2 Element<Channel>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.slist.element.repcap_channel_get()
driver.slist.element.repcap_channel_set(repcap.Channel.Nr1)
```

class ElementCls

Element commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Channel, default value after init: Channel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.element.clone()
```

Subgroups

6.14.2.1 Mapping

SCPI Command :

```
SLIST:ELEMENT<CH>:MAPPING
```

class MappingCls

Mapping commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*channel=Channel.Default*) → ErFpowSensMapping

```
# SCPI: SLIST:ELEMENT<CH>:MAPPING
value: enums.ErFpowSensMapping = driver.slist.element.mapping.get(channel = ↵
↵repcap.Channel.Default)
```

Assigns an entry from the method RsAreg.Slist.listPy to one of the four sensor channels.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Element’)

return

mapping: SENS1| SENSor1| SENS2| SENSor2| SENS3| SENSor3| SENS4| SENSor4| UNMapped Sensor channel.

set(*mapping: ErFpowSensMapping, channel=Channel.Default*) → None

```
# SCPI: SLIST:ELEMENT<CH>:MAPPING
driver.slist.element.mapping.set(mapping = enums.ErFpowSensMapping.SENS1, ↵
↵channel = repcap.Channel.Default)
```

Assigns an entry from the method RsAreg.Slist.listPy to one of the four sensor channels.

param mapping

SENS1| SENSor1| SENS2| SENSor2| SENS3| SENSor3| SENS4| SENSor4| UNMapped Sensor channel.

param channel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Element’)

6.14.3 Scan

SCPI Commands :

```
SLIST:SCAN:LENSor
SLIST:SCAN:[STATe]
```

class ScanCls

Scan commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_state() → bool

```
# SCPI: SLISt:SCAN:[STAtE]
value: bool = driver.slist.scan.get_state()
```

Starts the search for R&S NRP power sensors, connected in the LAN or via the USBTMC protocol.

return
state: 0| 1| OFF| ON

set_lsensor(ip: str) → None

```
# SCPI: SLISt:SCAN:LSENsor
driver.slist.scan.set_lsensor(ip = 'abc')
```

Scans for R&S NRP power sensors connected in the LAN.

param ip
string

set_state(state: bool) → None

```
# SCPI: SLISt:SCAN:[STAtE]
driver.slist.scan.set_state(state = False)
```

Starts the search for R&S NRP power sensors, connected in the LAN or via the USBTMC protocol.

param state
0| 1| OFF| ON

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.scan.clone()
```

Subgroups

6.14.3.1 Usensor

SCPI Command :

```
SLISt:SCAN:USENsor
```

class UsensorCls

Usensor commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(device_id: str, serial: int) → None

```
# SCPI: SLISt:SCAN:USENsor
driver.slist.scan.usensor.set(device_id = 'abc', serial = 1)
```

Scans for R&S NRP power sensors connected over a USB interface.

param device_id
String or Integer Range: 0 to 999999

param serial
integer Range: 0 to 999999

6.14.4 Sensor

class SensorCls

Sensor commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.slist.sensor.clone()
```

Subgroups

6.14.4.1 Map

SCPI Command :

```
SLISt:SENSor:MAP
```

class MapCls

Map commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(sensor_id: str, mapping: ErFpowSensMapping) → None

```
# SCPI: SLISt:SENSor:MAP
driver.slist.sensor.map.set(sensor_id = 'abc', mapping = enums.
↳ErFpowSensMapping.SENS1)
```

Assigns a sensor directly to one of the sensor channels, using the sensor name and serial number. To find out the the sensor name and ID, you can get it from the label of the R&S NRP, or using the command method RsAreg.Slist.Scan.state. This command detects all R&S NRP power sensors connected in the LAN or via 'USBTMC protocol.

param sensor_id
string

param mapping
enum

6.15 Source

SCPI Command :

```
SOURce<HW>:PRESet
```

class SourceCls

Source commands group definition. 47 total commands, 8 Subgroups, 1 group commands

preset() → None

```
# SCPI: SOURCE<HW>:PRESet
driver.source.preset()
```

Presets all parameters which are related to the selected signal path.

preset_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SOURCE<HW>:PRESet
driver.source.preset_with_opc()
```

Presets all parameters which are related to the selected signal path.

Same as preset, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.clone()
```

Subgroups

6.15.1 AreGenerator

class AreGeneratorCls

AreGenerator commands group definition. 31 total commands, 5 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.clone()
```

Subgroups

6.15.1.1 Channel

class ChannelCls

Channel commands group definition. 3 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.channel.clone()
```

Subgroups

6.15.1.1.1 InputPy

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:CHANnel:INPut:NOMGain
[SOURCE<HW>]:AREGenerator:CHANnel:INPut:RELLevel
```

class InputPyCls

InputPy commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_nom_gain() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:INPut:NOMGain
value: float = driver.source.areGenerator.channel.inputPy.get_nom_gain()
```

No command help available

```
return
    areg_chan_nom_gain: No help available
```

get_rel_level() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:INPut:RELLevel
value: float = driver.source.areGenerator.channel.inputPy.get_rel_level()
```

No command help available

```
return
    areg_chan_rel_lev: No help available
```

set_nom_gain(areg_chan_nom_gain: float) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:CHANnel:INPut:NOMGain
driver.source.areGenerator.channel.inputPy.set_nom_gain(areg_chan_nom_gain = 1.
↪0)
```

No command help available

```
param areg_chan_nom_gain
    No help available
```

6.15.1.1.2 Output

SCPI Command :

```
[SOURce<HW>]:AREGenerator:CHANnel:OUTPut:NOMGain
```

class OutputCls

Output commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_nom_gain() → float

```
# SCPI: [SOURce<HW>]:AREGenerator:CHANnel:OUTPut:NOMGain
value: float = driver.source.areGenerator.channel.output.get_nom_gain()
```

No command help available

return

areg_chan_nom_gain: No help available

set_nom_gain(areg_chan_nom_gain: float) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:CHANnel:OUTPut:NOMGain
driver.source.areGenerator.channel.output.set_nom_gain(areg_chan_nom_gain = 1.0)
```

No command help available

param areg_chan_nom_gain

No help available

6.15.1.2 Object<ObjectIx>

RepCap Settings

```
# Range: Nr1 .. Nr12
rc = driver.source.areGenerator.object.repcap_objectIx_get()
driver.source.areGenerator.object.repcap_objectIx_set(repcap.ObjectIx.Nr1)
```

class ObjectCls

Object commands group definition. 7 total commands, 5 Subgroups, 0 group commands Repeated Capability: ObjectIx, default value after init: ObjectIx.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.object.clone()
```

Subgroups

6.15.1.2.1 All

SCPI Command :

```
[SOURce<HW>]:AREGenerator:OBJECT:ALL:[STATe]
```

class AllCls

All commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURce<HW>]:AREGenerator:OBJECT:ALL:[STATe]
value: bool = driver.source.areGenerator.object.all.get_state()
```

Switches all available radar objects (1 to 4) on or off simultaneously.

```
return
    global_obj_stat: 0| 1| OFF| ON
```

set_state(global_obj_stat: bool) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:OBJECT:ALL:[STATe]
driver.source.areGenerator.object.all.set_state(global_obj_stat = False)
```

Switches all available radar objects (1 to 4) on or off simultaneously.

```
param global_obj_stat
    0| 1| OFF| ON
```

6.15.1.2.2 Attenuation

SCPI Command :

```
[SOURce<HW>]:AREGenerator:OBJECT<CH>:ATTenuation
```

class AttenuationCls

Attenuation commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(objectIx=ObjectIx.Default) → float

```
# SCPI: [SOURce<HW>]:AREGenerator:OBJECT<CH>:ATTenuation
value: float = driver.source.areGenerator.object.attenuation.get(objectIx = ↵
↵repcap.ObjectIx.Default)
```

Sets the attenuation of a specific radar object. Together with the base attenuation that applies to all radar objects, it forms the total attenuation for the specific object.

```
param objectIx
    optional repeated capability selector. Default value: Nr1 (settable in the interface 'Ob-
    ject')
```

```
return
    areg_obj_att: float Range: 0 to 63.5
```

set(*areg_obj_att*: float, *objectIx*=ObjectIx.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:ATTenuation
driver.source.areGenerator.object.attenuation.set(areg_obj_att = 1.0, objectIx_
↪= repcap.ObjectIx.Default)
```

Sets the attenuation of a specific radar object. Together with the base attenuation that applies to all radar objects, it forms the total attenuation for the specific object.

param areg_obj_att
float Range: 0 to 63.5

param objectIx
optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Object’)

6.15.1.2.3 Range

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:RANGe
```

class RangeCls

Range commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*objectIx*=ObjectIx.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:RANGe
value: float = driver.source.areGenerator.object.range.get(objectIx = repcap.
↪ObjectIx.Default)
```

Queries the object’s range. The value is the sum of the fixed delay (depending on the installed option) and the air gap between DUT and R&S AREG100A.

param objectIx
optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Object’)

return
areg_obj_range: float Range: depends on settings

6.15.1.2.4 Rcs

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:RCS
```

class RcsCls

Rcs commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*objectIx*=ObjectIx.Default) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:RCS
value: float = driver.source.areGenerator.object.rcs.get(objectIx = repcap.
↳ObjectIx.Default)
```

Queries the calculated radar cross section of an object.

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

return

areg_obj_rcs: float Range: -100 to 100

6.15.1.2.5 SubChannel<Subchannel>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.source.areGenerator.object.subChannel.repcap_subchannel_get()
driver.source.areGenerator.object.subChannel.repcap_subchannel_set(repcap.Subchannel.Nr1)
```

class SubChannelCls

SubChannel commands group definition. 3 total commands, 2 Subgroups, 0 group commands Repeated Capability: Subchannel, default value after init: Subchannel.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.object.subChannel.clone()
```

Subgroups

6.15.1.2.5.1 Doppler

class DopplerCls

Doppler commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.object.subChannel.doppler.clone()
```

Subgroups

6.15.1.2.5.2 Frequency

SCPI Command :

`[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPler:FREQuency`

class FrequencyCls

Frequency commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*objectIx=ObjectIx.Default, subchannel=Subchannel.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPler:FREQuency
value: float = driver.source.areGenerator.object.subChannel.doppler.frequency.
↪get(objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.
↪Default)
```

No command help available

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Object’)

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘SubChannel’)

return

areg_ob_dopp_freq: No help available

set(*areg_ob_dopp_freq: float, objectIx=ObjectIx.Default, subchannel=Subchannel.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPler:FREQuency
driver.source.areGenerator.object.subChannel.doppler.frequency.set(areg_ob_dopp_
↪freq = 1.0, objectIx = repcap.ObjectIx.Default, subchannel = repcap.
↪Subchannel.Default)
```

No command help available

param areg_ob_dopp_freq

No help available

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Object’)

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘SubChannel’)

6.15.1.2.5.3 Speed

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPler:[SPEed]
```

class SpeedCls

Speed commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*objectIx=ObjectIx.Default, subchannel=Subchannel.Default*) → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPler:[SPEed]
value: float = driver.source.areGenerator.object.subChannel.doppler.speed.
↪get(objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.
↪Default)
```

No command help available

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

return

areg_object_dopp: No help available

set(*areg_object_dopp: float, objectIx=ObjectIx.Default, subchannel=Subchannel.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:DOPPler:[SPEed]
driver.source.areGenerator.object.subChannel.doppler.speed.set(areg_object_dopp,
↪= 1.0, objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.
↪Default)
```

No command help available

param areg_object_dopp

No help available

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

6.15.1.2.5.4 State

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:[STATE]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*objectIx=ObjectIx.Default, subchannel=Subchannel.Default*) → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:[STATE]
value: bool = driver.source.areGenerator.object.subChannel.state.get(objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.Default)
```

No command help available

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

return

areg_obj_state: No help available

set(*areg_obj_state: bool, objectIx=ObjectIx.Default, subchannel=Subchannel.Default*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OBJECT<CH>:[SUBChannel<ST>]:[STATE]
driver.source.areGenerator.object.subChannel.state.set(areg_obj_state = False, objectIx = repcap.ObjectIx.Default, subchannel = repcap.Subchannel.Default)
```

No command help available

param areg_obj_state

No help available

param objectIx

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Object')

param subchannel

optional repeated capability selector. Default value: Nr1 (settable in the interface 'SubChannel')

6.15.1.3 Osetup

class OsetupCls

Osetup commands group definition. 5 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.osetup.clone()
```

Subgroups

6.15.1.3.1 MultiInstrument

class MultiInstrumentCls

MultiInstrument commands group definition. 5 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.osetup.multiInstrument.clone()
```

Subgroups

6.15.1.3.1.1 Connect

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:CONNECT
```

class ConnectCls

Connect commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:CONNECT
driver.source.areGenerator.osetup.multiInstrument.connect.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:CONNECT
driver.source.areGenerator.osetup.multiInstrument.connect.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.15.1.3.1.2 Remove

class RemoveCls

Remove commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.osetup.multiInstrument.remove.clone()
```

Subgroups

6.15.1.3.1.3 Execute

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:REMove:EXECute
```

class ExecuteCls

Execute commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:REMove:EXECute
driver.source.areGenerator.osetup.multiInstrument.remove.execute.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:REMove:EXECute
driver.source.areGenerator.osetup.multiInstrument.remove.execute.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.15.1.3.1.4 Secondary<Index>

RepCap Settings

```
# Range: Nr1 .. Nr64
rc = driver.source.areGenerator.oseup.multiInstrument.secondary.repcap_index_get()
driver.source.areGenerator.oseup.multiInstrument.secondary.repcap_index_set(repcap.
↳ Index.Nr1)
```

class SecondaryCls

Secondary commands group definition. 3 total commands, 3 Subgroups, 0 group commands Repeated Capability: Index, default value after init: Index.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.oseup.multiInstrument.secondary.clone()
```

Subgroups

6.15.1.3.1.5 Add

SCPI Command :

```
[SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:ADD
```

class AddCls

Add commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:ADD
driver.source.areGenerator.oseup.multiInstrument.secondary.add.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:ADD
driver.source.areGenerator.oseup.multiInstrument.secondary.add.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.15.1.3.1.6 Execute

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:EXECute
```

class ExecuteCls

Execute commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:EXECute
driver.source.areGenerator.oseSetup.multiInstrument.secondary.execute.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary:EXECute
driver.source.areGenerator.oseSetup.multiInstrument.secondary.execute.set_with_
↳opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.15.1.3.1.7 Remove

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary<ST>:REMOve
```

class RemoveCls

Remove commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(index=Index.Default) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECondary<ST>:REMOve
driver.source.areGenerator.oseSetup.multiInstrument.secondary.remove.set(index =
↳repcap.Index.Default)
```

No command help available

param index

optional repeated capability selector. Default value: Nr1 (settable in the interface 'Secondary')

set_with_opc(index=Index.Default, opc_timeout_ms: int = -1) → None

6.15.1.4 Radar

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:RADar:LSensitivity
```

class RadarCls

Radar commands group definition. 10 total commands, 6 Subgroups, 1 group commands

get_lsensitivity() → bool

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:LSensitivity
value: bool = driver.source.areGenerator.radar.get_lsensitivity()
```

Defines if low sensitivity is used or not.

```
return
    areg_radar_low_sen: 0| 1| OFF| ON
```

set_lsensitivity(areg_radar_low_sen: bool) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:LSensitivity
driver.source.areGenerator.radar.set_lsensitivity(areg_radar_low_sen = False)
```

Defines if low sensitivity is used or not.

```
param areg_radar_low_sen
    0| 1| OFF| ON
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.radar.clone()
```

Subgroups

6.15.1.4.1 Antenna

class AntennaCls

Antenna commands group definition. 3 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.radar.antenna.clone()
```

Subgroups

6.15.1.4.1.1 Custom

SCPI Command :

```
[SOURce<HW>]:AREGenerator:RADar:ANTenna:CUSTom:[STATe]
```

class CustomCls

Custom commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURce<HW>]:AREGenerator:RADar:ANTenna:CUSTom:[STATe]
value: bool = driver.source.areGenerator.radar.antenna.custom.get_state()

INTRO_CMD_HELP: If enabled, you can use a custom antenna and define the
↳transmitting and receiving gain values with the commands:

- [:SOURce<hw>]:AREGenerator:RADar:ANTenna:REG:GAIN:TX
- [:SOURce<hw>]:AREGenerator:RADar:ANTenna:REG:GAIN:RX.

: return: areg_ant_cust_stat: 0 | 1 | OFF | ON 0 | OFF The predefined antenna
↳gain settings for transmitting and receiving antenna are used. 1 | ON The
↳customer-specific antenna gain settings for transmitting and receiving
↳antenna apply.
```

set_state(areg_ant_cust_stat: bool) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:RADar:ANTenna:CUSTom:[STATe]
driver.source.areGenerator.radar.antenna.custom.set_state(areg_ant_cust_stat =
↳False)

INTRO_CMD_HELP: If enabled, you can use a custom antenna and define the
↳transmitting and receiving gain values with the commands:

- [:SOURce<hw>]:AREGenerator:RADar:ANTenna:REG:GAIN:TX
- [:SOURce<hw>]:AREGenerator:RADar:ANTenna:REG:GAIN:RX.

: param areg_ant_cust_stat: 0 | 1 | OFF | ON 0 | OFF The predefined antenna
↳gain settings for transmitting and receiving antenna are used. 1 | ON The
↳customer-specific antenna gain settings for transmitting and receiving
↳antenna apply.
```

6.15.1.4.1.2 Reg

class RegCls

Reg commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.areGenerator.radar.antenna.reg.clone()
```

Subgroups

6.15.1.4.1.3 Gain

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:RADar:ANTenna:REG:GAIN:RX
[SOURCE<HW>]:AREGenerator:RADar:ANTenna:REG:GAIN:TX
```

class GainCls

Gain commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_rx() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:ANTenna:REG:GAIN:RX
value: int = driver.source.areGenerator.radar.antenna.reg.gain.get_rx()
```

Queries the antenna gain of the transmitting/receiving antenna. If [SOURCE<hw>]:AREGenerator:RADar:ANTenna:CUSTom[:STATE]1, you can define a customer-specific antenna gain value.

return
areg_ant_gain_rx: integer Range: 0 to 30

get_tx() → int

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:ANTenna:REG:GAIN:TX
value: int = driver.source.areGenerator.radar.antenna.reg.gain.get_tx()
```

Queries the antenna gain of the transmitting/receiving antenna. If [SOURCE<hw>]:AREGenerator:RADar:ANTenna:CUSTom[:STATE]1, you can define a customer-specific antenna gain value.

return
areg_ant_gain_tx: No help available

set_rx(areg_ant_gain_rx: int) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:ANTenna:REG:GAIN:RX
driver.source.areGenerator.radar.antenna.reg.gain.set_rx(areg_ant_gain_rx = 1)
```

Queries the antenna gain of the transmitting/receiving antenna. If [:SOURce<hw>]:AREGenerator:RADar:ANTenna:CUSTom[:STATe]1, you can define a customer-specific antenna gain value.

param areg_ant_gain_rx
integer Range: 0 to 30

set_tx(areg_ant_gain_tx: int) → None

```
# SCPI: [:SOURce<HW>]:AREGenerator:RADar:ANTenna:REG:GAIN:TX
driver.source.areGenerator.radar.antenna.reg.gain.set_tx(areg_ant_gain_tx = 1)
```

Queries the antenna gain of the transmitting/receiving antenna. If [:SOURce<hw>]:AREGenerator:RADar:ANTenna:CUSTom[:STATe]1, you can define a customer-specific antenna gain value.

param areg_ant_gain_tx
integer Range: 0 to 30

6.15.1.4.2 Base

SCPI Command :

```
[SOURce<HW>]:AREGenerator:RADar:BASE:ATTenuation
```

class BaseCls

Base commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_attenuation() → int

```
# SCPI: [:SOURce<HW>]:AREGenerator:RADar:BASE:ATTenuation
value: int = driver.source.areGenerator.radar.base.get_attenuation()
```

Defines the attenuation affecting all radar objects. Together with the individual attenuation for a single radar object, it forms the total attenuation for the specific object.

return
areg_base_att: integer Range: -50 to 150, Unit: dB

set_attenuation(areg_base_att: int) → None

```
# SCPI: [:SOURce<HW>]:AREGenerator:RADar:BASE:ATTenuation
driver.source.areGenerator.radar.base.set_attenuation(areg_base_att = 1)
```

Defines the attenuation affecting all radar objects. Together with the individual attenuation for a single radar object, it forms the total attenuation for the specific object.

param areg_base_att
integer Range: -50 to 150, Unit: dB

6.15.1.4.3 Dbypass

SCPI Command :

```
[SOURce<HW>]:AREGenerator:RADar:DBYPass:[STATe]
```

class DbypassCls

Dbypass commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURce<HW>]:AREGenerator:RADar:DBYPass:[STATe]
value: bool = driver.source.areGenerator.radar.dbypass.get_state()
```

Enable to bypass the Doppler stage. For details, see ‘Enable Doppler Bypass’.

```
return
    areg_radar_dop_byp: 0| 1| OFF| ON
```

set_state(areg_radar_dop_byp: bool) → None

```
# SCPI: [SOURce<HW>]:AREGenerator:RADar:DBYPass:[STATe]
driver.source.areGenerator.radar.dbypass.set_state(areg_radar_dop_byp = False)
```

Enable to bypass the Doppler stage. For details, see ‘Enable Doppler Bypass’.

```
param areg_radar_dop_byp
    0| 1| OFF| ON
```

6.15.1.4.4 Eirp

SCPI Commands :

```
[SOURce<HW>]:AREGenerator:RADar:EIRP:SENSor
[SOURce<HW>]:AREGenerator:RADar:EIRP
```

class EirpCls

Eirp commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_sensor() → AregPowSens

```
# SCPI: [SOURce<HW>]:AREGenerator:RADar:EIRP:SENSor
value: enums.AregPowSens = driver.source.areGenerator.radar.eirp.get_sensor()
```

Queries if and which sensor is used to measure the EIRP value.

```
return
    areg_pow_sen_selec: SEN4| SEN3| SEN2| SEN1| UDEfined UDEfined No sensor
    is selected for EIRP measurement. However, there can be power sensors connected
    to one of the ‘USB’ connectors or the ‘Sensor’ connector of the R&S AREG100A.
    Sent the method RsAreg.Slist.listPy query to find out if and which power sensors
    are connected to the instrument. SEN4|SEN3|SEN2|SEN1 Indicates that a power sensor
    is connected to the frontend. The number SENx indicates the subsequent number in
    the sensor mapping list of the corresponding sensor. Observe the most left column in
    the ‘NRP Sensor Mapping’ dialog. See method RsAreg.Slist.Element.Mapping.set.
```

get_value() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:EIRP
value: float = driver.source.areGenerator.radar.eirp.get_value()
```

Queries the measured EIRP value of the radar sensor. For details, see ‘EIRP calculation’.

return
 areg_radar_eirp: float Range: -150 to 150

set_sensor(*areg_pow_sen_selec: AregPowSens*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:EIRP:SENSor
driver.source.areGenerator.radar.eirp.set_sensor(areg_pow_sen_selec = enums.
↳AregPowSens.SEN1)
```

Queries if and which sensor is used to measure the EIRP value.

param areg_pow_sen_selec
 SEN4| SEN3| SEN2| SEN1| UDEfined UDEfined No sensor is selected for EIRP measurement. However, there can be power sensors connected to one of the ‘USB’ connectors or the ‘Sensor’ connector of the R&S AREG100A. Sent the method RsAreg.Slist.listPy query to find out if and which power sensors are connected to the instrument. SEN4|SEN3|SEN2|SEN1 Indicates that a power sensor is connected to the frontend. The number SENx indicates the subsequent number in the sensor mapping list of the corresponding sensor. Observe the most left column in the ‘NRP Sensor Mapping’ dialog. See method RsAreg.Slist.Element.Mapping.set.

6.15.1.4.5 Ota

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:RADar:OTA:OFFSet
```

class OtaCls

Ota commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_offset() → float

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:OTA:OFFSet
value: float = driver.source.areGenerator.radar.ota.get_offset()
```

Defines the distance (air gap) from the R&S AREG100A to the RUT (radar under test) .

return
 areg_ota_offset: float Range: 0.01 to 10, Unit: m

set_offset(*areg_ota_offset: float*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:OTA:OFFSet
driver.source.areGenerator.radar.ota.set_offset(areg_ota_offset = 1.0)
```

Defines the distance (air gap) from the R&S AREG100A to the RUT (radar under test) .

param areg_ota_offset
 float Range: 0.01 to 10, Unit: m

6.15.1.4.6 Power

SCPI Command :

```
[SOURCE<HW>]:AREGenerator:RADar:POWer:INDicator
```

class PowerCls

Power commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_indicator() → AregRadarPowIndicator

```
# SCPI: [SOURCE<HW>]:AREGenerator:RADar:POWer:INDicator
value: enums.AregRadarPowIndicator = driver.source.areGenerator.radar.power.get_
indicator()
```

The radar power indicator is a summary indicator for all radar object powers.

return

pow_indicator: OFF| GOOD| WEAK| BAD OFF No or very weak RX power is detected. GOOD The RX power is in linear range. WEAK The RX power is strong, non-linear effects can occur. BAD The RX power is in a range, where the receiver is in saturation.

6.15.1.5 Units

SCPI Commands :

```
[SOURCE<HW>]:AREGenerator:UNITs:ANGLE
[SOURCE<HW>]:AREGenerator:UNITs:DOPPler
[SOURCE<HW>]:AREGenerator:UNITs:RANGe
[SOURCE<HW>]:AREGenerator:UNITs:RCS
[SOURCE<HW>]:AREGenerator:UNITs:SHIFt
[SOURCE<HW>]:AREGenerator:UNITs:SPEed
```

class UnitsCls

Units commands group definition. 6 total commands, 0 Subgroups, 6 group commands

get_angle() → UnitAngleAreg

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:ANGLE
value: enums.UnitAngleAreg = driver.source.areGenerator.units.get_angle()
```

No command help available

return

areg_unit_agle: No help available

get_doppler() → AregDopplerUnit

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:DOPPler
value: enums.AregDopplerUnit = driver.source.areGenerator.units.get_doppler()
```

Defines if the radial velocity is defined as Doppler speed or frequency.

```

    return
    areg_obj_dopp_unit: SPEed|FREQuency

```

get_range() → UnitLengthAreg

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:RANGe
value: enums.UnitLengthAreg = driver.source.areGenerator.units.get_range()

```

Defines the range unit.

```

    return
    areg_unit_range: M|CM|FT M Meter CM Centimeter FT Feet

```

get_rcs() → UnitRcsAreg

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:RCS
value: enums.UnitRcsAreg = driver.source.areGenerator.units.get_rcs()

```

Defines the unit of the radar cross section.

```

    return
    areg_unit_rcs: DBSM|SM DBSM dB relative to one square meter. SM m2 (square
    meters) .

```

get_shift() → UnitShiftAreg

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:SHIFt
value: enums.UnitShiftAreg = driver.source.areGenerator.units.get_shift()

```

No command help available

```

    return
    areg_unit_shift: No help available

```

get_speed() → UnitSpeedAreg

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:SPEed
value: enums.UnitSpeedAreg = driver.source.areGenerator.units.get_speed()

```

Defines the speed unit.

```

    return
    areg_unit_speed: KMH|MPH|MPS KMH Kilometer per hour MPH Miles per Hour
    MPS Meter per Seconds

```

set_angle(areg_unit_agle: UnitAngleAreg) → None

```

# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:ANGLe
driver.source.areGenerator.units.set_angle(areg_unit_agle = enums.UnitAngleAreg.
↪DEGREE)

```

No command help available

```

    param areg_unit_agle
    No help available

```

set_doppler(areg_obj_dopp_unit: AregDopplerUnit) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:DOPPler
driver.source.areGenerator.units.set_doppler(areg_obj_dopp_unit = enums.
↳AregDopplerUnit.FREQuency)
```

Defines if the radial velocity is defined as Doppler speed or frequency.

param areg_obj_dopp_unit
SPEed| FREQuency

set_range(areg_unit_range: *UnitLengthAreg*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:RANGe
driver.source.areGenerator.units.set_range(areg_unit_range = enums.
↳UnitLengthAreg.CM)
```

Defines the range unit.

param areg_unit_range
M| CM| FT M Meter CM Centimeter FT Feet

set_rcs(areg_unit_rcs: *UnitRcsAreg*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:RCS
driver.source.areGenerator.units.set_rcs(areg_unit_rcs = enums.UnitRcsAreg.DBSM)
```

Defines the unit of the radar cross section.

param areg_unit_rcs
DBSM| SM DBSM dB relative to one square meter. SM m2 (square meters) .

set_shift(areg_unit_shift: *UnitShiftAreg*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:SHIFt
driver.source.areGenerator.units.set_shift(areg_unit_shift = enums.
↳UnitShiftAreg.HZ)
```

No command help available

param areg_unit_shift
No help available

set_speed(areg_unit_speed: *UnitSpeedAreg*) → None

```
# SCPI: [SOURCE<HW>]:AREGenerator:UNITs:SPEEd
driver.source.areGenerator.units.set_speed(areg_unit_speed = enums.
↳UnitSpeedAreg.KMH)
```

Defines the speed unit.

param areg_unit_speed
KMH| MPH| MPS KMH Kilometer per hour MPH Miles per Hour MPS Meter per
Seconds

6.15.2 Bb

class BbCls

Bb commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.bb.clone()
```

Subgroups

6.15.2.1 Path

SCPI Command :

```
[SOURce]:BB:PATH:COUNT
```

class PathCls

Path commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_count() → int

```
# SCPI: [SOURce]:BB:PATH:COUNT
value: int = driver.source.bb.path.get_count()
```

No command help available

return
count: No help available

6.15.3 Frequency

class FrequencyCls

Frequency commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.frequency.clone()
```

Subgroups

6.15.3.1 Cw

SCPI Commands :

```
[SOURCE<HW>]:FREQUENCY:[CW]:RCL
[SOURCE<HW>]:FREQUENCY:[CW]
```

class CwCls

Cw commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_recall() → InclExcl

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]:RCL
value: enums.InclExcl = driver.source.frequency.cw.get_recall()
```

Set whether the RF frequency value is retained or taken from a loaded instrument configuration, when you recall instrument settings with command *RCL.

return

rcl: INCLude| EXCLude INCLude Takes the frequency value of the loaded settings.
EXCLude Retains the current frequency when an instrument configuration is loaded.

get_value() → float

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]
value: float = driver.source.frequency.cw.get_value()
```

R&S AREG-B124/-B177: queries the center frequency. R&S AREG-B181: sets the center frequency of the RF output signal.

return

frequency: float Range: R&S AREG-B124: 24 GHz, R&S AREG-B177: 77 GHz,
R&S AREG-B181: 78 GHz and 79 GHz

set_recall(rcl: InclExcl) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]:RCL
driver.source.frequency.cw.set_recall(rcl = enums.InclExcl.EXCLude)
```

Set whether the RF frequency value is retained or taken from a loaded instrument configuration, when you recall instrument settings with command *RCL.

param rcl

INCLude| EXCLude INCLude Takes the frequency value of the loaded settings. EX-
CLude Retains the current frequency when an instrument configuration is loaded.

set_value(frequency: float) → None

```
# SCPI: [SOURCE<HW>]:FREQUENCY:[CW]
driver.source.frequency.cw.set_value(frequency = 1.0)
```

R&S AREG-B124/-B177: queries the center frequency. R&S AREG-B181: sets the center frequency of the RF output signal.

param frequency

float Range: R&S AREG-B124: 24 GHz, R&S AREG-B177: 77 GHz, R&S AREG-B181: 78 GHz and 79 GHz

6.15.4 InputPy

class InputPyCls

InputPy commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.inputPy.clone()
```

Subgroups

6.15.4.1 Trigger

SCPI Command :

```
[SOURce]:INPut:TRIGger:SLOPe
```

class TriggerCls

Trigger commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_slope() → SlopeType

```
# SCPI: [SOURce]:INPut:TRIGger:SLOPe
value: enums.SlopeType = driver.source.inputPy.trigger.get_slope()
```

No command help available

return

slope: No help available

set_slope(slope: SlopeType) → None

```
# SCPI: [SOURce]:INPut:TRIGger:SLOPe
driver.source.inputPy.trigger.set_slope(slope = enums.SlopeType.NEGative)
```

No command help available

param slope

No help available

6.15.5 Modulation

class ModulationCls

Modulation commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.modulation.clone()
```

Subgroups

6.15.5.1 All

SCPI Command :

```
[SOURCE<HW>]:MODulation:[ALL]:[STATE]
```

class AllCls

All commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURCE<HW>]:MODulation:[ALL]:[STATE]
value: bool = driver.source.modulation.all.get_state()
```

No command help available

return
state: No help available

set_state(state: bool) → None

```
# SCPI: [SOURCE<HW>]:MODulation:[ALL]:[STATE]
driver.source.modulation.all.set_state(state = False)
```

No command help available

param state
No help available

6.15.6 Path

SCPI Command :

```
[SOURCE]:PATH:COUNT
```

class PathCls

Path commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_count() → int

```
# SCPI: [SOURCE]:PATH:COUNT
value: int = driver.source.path.get_count()
```

No command help available

```
return
count: No help available
```

6.15.7 Power

class PowerCls

Power commands group definition. 3 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.clone()
```

Subgroups

6.15.7.1 Level

class LevelCls

Level commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.level.clone()
```

Subgroups

6.15.7.1.1 Immediate

SCPI Command :

```
[SOURCE<HW>]:POWER:[LEVEL]:[IMMEDIATE]:RCL
```

class ImmediateCls

Immediate commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_recall() → InclExcl

```
# SCPI: [SOURCE<HW>]:POWER:[LEVEL]:[IMMEDIATE]:RCL
value: enums.InclExcl = driver.source.power.level.immediate.get_recall()
```

No command help available

return

rcl: No help available

set_recall(rcl: InclExcl) → None

```
# SCPI: [SOURCE<HW>]:POWER:[LEVEL]:[IMMEDIATE]:RCL
driver.source.power.level.immediate.set_recall(rcl = enums.InclExcl.EXCLUDE)
```

No command help available

param rcl

No help available

6.15.7.2 Spc

class SpcCls

Spc commands group definition. 2 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.power.spc.clone()
```

Subgroups

6.15.7.2.1 Measure

SCPI Command :

```
[SOURCE<HW>]:POWER:SPC:MEASure
```

class MeasureCls

Measure commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURCE<HW>]:POWER:SPC:MEASure
driver.source.power.spc.measure.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURCE<HW>]:POWER:SPC:MEASure
driver.source.power.spc.measure.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.15.7.2.2 Single

SCPI Command :

```
[SOURce<HW>]:POWer:SPC:SINGle
```

class SingleCls

Single commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: [SOURce<HW>]:POWer:SPC:SINGle
driver.source.power.spc.single.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: [SOURce<HW>]:POWer:SPC:SINGle
driver.source.power.spc.single.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.15.8 Roscillator

SCPI Command :

```
[SOURce]:ROSCillator:SOURce
```

class RoscillatorCls

Roscillator commands group definition. 6 total commands, 2 Subgroups, 1 group commands

get_source() → RoscSourSetup

```
# SCPI: [SOURce]:ROSCillator:SOURce
value: enums.RoscSourSetup = driver.source.roscillator.get_source()
```

Selects between internal or external reference frequency.

return

source: INTernal| EXTernal

set_source(source: RoscSourSetup) → None

```
# SCPI: [SOURCE]:ROSCillator:SOURce
driver.source.roscillator.set_source(source = enums.RoscSourSetup.ELoop)
```

Selects between internal or external reference frequency.

```
param source
    INTernal| EXTernal
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.roscillator.clone()
```

Subgroups

6.15.8.1 External

SCPI Commands :

```
[SOURCE]:ROSCillator:EXTernal:FREquency
[SOURCE]:ROSCillator:EXTernal:SBANdwidth
```

class ExternalCls

External commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_frequency() → RoscFreqExt

```
# SCPI: [SOURCE]:ROSCillator:EXTernal:FREquency
value: enums.RoscFreqExt = driver.source.roscillator.external.get_frequency()
```

No command help available

```
return
    frequency: No help available
```

get_sbandwidth() → RoscBandWidtExt

```
# SCPI: [SOURCE]:ROSCillator:EXTernal:SBANdwidth
value: enums.RoscBandWidtExt = driver.source.roscillator.external.get_
↳ sbandwidth()
```

No command help available

```
return
    sbandwidth: No help available
```

set_frequency(frequency: RoscFreqExt) → None

```
# SCPI: [SOURCE]:ROSCillator:EXTernal:FREquency
driver.source.roscillator.external.set_frequency(frequency = enums.RoscFreqExt._
↳ 10MHZ)
```

No command help available

param frequency

No help available

set_sbandwidth(sbandwidth: *RoscBandWidtExt*) → None

```
# SCPI: [SOURce]:ROSCillator:EXternal:SBANdwidth
driver.source.roscillator.external.set_sbandwidth(sbandwidth = enums.
↳RoscBandWidtExt.NARRow)
```

No command help available

param sbandwidth

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.roscillator.external.clone()
```

Subgroups

6.15.8.1.1 RfOff

SCPI Command :

```
[SOURce]:ROSCillator:EXternal:RFOff: [STATe]
```

class RfOffCls

RfOff commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: [SOURce]:ROSCillator:EXternal:RFOff: [STATe]
value: bool = driver.source.roscillator.external.rfOff.get_state()
```

No command help available

return

state: No help available

set_state(state: bool) → None

```
# SCPI: [SOURce]:ROSCillator:EXternal:RFOff: [STATe]
driver.source.roscillator.external.rfOff.set_state(state = False)
```

No command help available

param state

No help available

6.15.8.2 Internal

class InternalCls

Internal commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.source.roscillator.internal.clone()
```

Subgroups

6.15.8.2.1 Adjust

SCPI Commands :

```
[SOURce]:ROSCillator:[INTernal]:ADJust:VALue
[SOURce]:ROSCillator:[INTernal]:ADJust:[STATe]
```

class AdjustCls

Adjust commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_state() → bool

```
# SCPI: [SOURce]:ROSCillator:[INTernal]:ADJust:[STATe]
value: bool = driver.source.roscillator.internal.adjust.get_state()
```

Determines whether the calibrated (off) or a user-defined (on) adjustment value is used for fine adjustment of the frequency.

return

state: 0| 1| OFF| ON 0 Fine adjustment with the calibrated frequency value 1 User-defined adjustment value. The instrument is no longer in the calibrated state. The calibration value is, however, not changed. The instrument resumes the calibrated state if you send SOURce:ROSCillator:INTernal:ADJust:STATe 0.

get_value() → int

```
# SCPI: [SOURce]:ROSCillator:[INTernal]:ADJust:VALue
value: int = driver.source.roscillator.internal.adjust.get_value()
```

No command help available

return

value: No help available

set_state(state: bool) → None

```
# SCPI: [SOURce]:ROSCillator:[INTernal]:ADJust:[STATe]
driver.source.roscillator.internal.adjust.set_state(state = False)
```

Determines whether the calibrated (off) or a user-defined (on) adjustment value is used for fine adjustment of the frequency.

param state

0| 1| OFF| ON 0 Fine adjustment with the calibrated frequency value 1 User-defined adjustment value. The instrument is no longer in the calibrated state. The calibration value is, however, not changed. The instrument resumes the calibrated state if you send SOURce:ROSCillator:INTernal:ADJust:STATe 0.

set_value(value: int) → None

```
# SCPI: [SOURce]:ROSCillator:[INTernal]:ADJust:VALue
driver.source.roscillator.internal.adjust.set_value(value = 1)
```

No command help available

param value

No help available

6.16 Status

SCPI Command :

```
STATus:PRESet
```

class StatusCls

Status commands group definition. 22 total commands, 3 Subgroups, 1 group commands

get_preset() → str

```
# SCPI: STATus:PRESet
value: str = driver.status.get_preset()
```

Resets the status registers. All PTRansition parts are set to FFFFh (32767) , i.e. all transitions from 0 to 1 are detected. All NTRansition parts are set to 0, i.e. a transition from 1 to 0 in a CONDition bit is not detected. The ENABLE parts of STATus:OPERation and STATus:QUEStionable are set to 0, i.e. all events in these registers are not passed on.

return

preset: string

set_preset(preset: str) → None

```
# SCPI: STATus:PRESet
driver.status.set_preset(preset = 'abc')
```

Resets the status registers. All PTRansition parts are set to FFFFh (32767) , i.e. all transitions from 0 to 1 are detected. All NTRansition parts are set to 0, i.e. a transition from 1 to 0 in a CONDition bit is not detected. The ENABLE parts of STATus:OPERation and STATus:QUEStionable are set to 0, i.e. all events in these registers are not passed on.

param preset

string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.clone()
```

Subgroups

6.16.1 Operation

SCPI Commands :

```
STATUS:OPERation:CONDition
STATUS:OPERation:ENABle
STATUS:OPERation:NTRansition
STATUS:OPERation:PTRansition
STATUS:OPERation:[EVENTt]
```

class OperationCls

Operation commands group definition. 10 total commands, 1 Subgroups, 5 group commands

get_condition() → str

```
# SCPI: STATUS:OPERation:CONDition
value: str = driver.status.operation.get_condition()
```

Queries the content of the CONDition part of the STATUS:OPERation register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out because it indicates the current hardware status.

return
condition: string

get_enable() → str

```
# SCPI: STATUS:OPERation:ENABle
value: str = driver.status.operation.get_enable()
```

Sets the bits of the ENABle part of the STATUS:OPERation register. This setting determines which events of the Status-Event part are forwarded to the sum bit in the status byte. These events can be used for a service request.

return
enable: string

get_event() → str

```
# SCPI: STATUS:OPERation:[EVENTt]
value: str = driver.status.operation.get_event()
```

Queries the content of the EVENTt part of the STATUS:OPERation register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENTt part is deleted after being read out.

return
value: No help available

get_ntransition() → str

```
# SCPI: STATUS:OPERation:NTRansition
value: str = driver.status.operation.get_ntransition()
```

Sets the bits of the NTRansition part of the STATUS:OPERation register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register. The disappearance of an event in the hardware is thus registered, for example the end of an adjustment.

return
ntransition: string

get_ptransition() → str

```
# SCPI: STATUS:OPERation:PTRansition
value: str = driver.status.operation.get_ptransition()
```

Sets the bits of the PTRansition part of the STATUS:OPERation register. If a bit is set, a transition from 0 to 1 in the condition part causes an entry to be made in the EVENT part of the register. A new event in the hardware is thus registered, for example the start of an adjustment.

return
ptransition: string

set_enable(enable: str) → None

```
# SCPI: STATUS:OPERation:ENABLE
driver.status.operation.set_enable(enable = 'abc')
```

Sets the bits of the ENABLE part of the STATUS:OPERation register. This setting determines which events of the Status-Event part are forwarded to the sum bit in the status byte. These events can be used for a service request.

param enable
string

set_event(value: str) → None

```
# SCPI: STATUS:OPERation:[EVENT]
driver.status.operation.set_event(value = 'abc')
```

Queries the content of the EVENT part of the STATUS:OPERation register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

param value
string

set_ntransition(ntransition: str) → None

```
# SCPI: STATUS:OPERation:NTRansition
driver.status.operation.set_ntransition(ntransition = 'abc')
```

Sets the bits of the NTRansition part of the STATUS:OPERation register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register. The disappearance of an event in the hardware is thus registered, for example the end of an adjustment.

param ntransition
string

set_ptransition(ptransition: str) → None

```
# SCPI: STATus:OPERation:PTRansition
driver.status.operation.set_ptransition(ptransition = 'abc')
```

Sets the bits of the PTRansition part of the STATus:OPERation register. If a bit is set, a transition from 0 to 1 in the condition part causes an entry to be made in the EVENT part of the register. A new event in the hardware is thus registered, for example the start of an adjustment.

param ptransition
string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.operation.clone()
```

Subgroups

6.16.1.1 Bit<BitNumberNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.status.operation.bit.repcap_bitNumberNull_get()
driver.status.operation.bit.repcap_bitNumberNull_set(repcap.BitNumberNull.Nr0)
```

class BitCls

Bit commands group definition. 5 total commands, 5 Subgroups, 0 group commands Repeated Capability: BitNumberNull, default value after init: BitNumberNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.operation.bit.clone()
```

Subgroups

6.16.1.1.1 Condition

SCPI Command :

```
STATus:OPERation:BIT<BITNR>:CONDition
```

class ConditionCls

Condition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:CONDition
value: str = driver.status.operation.bit.condition.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

condition: No help available

6.16.1.1.2 Enable

SCPI Command :

```
STATus:OPERation:BIT<BITNR>:ENABLE
```

class EnableCls

Enable commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:ENABLE
value: str = driver.status.operation.bit.enable.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

enable: No help available

set(*enable: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:OPERation:BIT<BITNR>:ENABLE
driver.status.operation.bit.enable.set(enable = 'abc', bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

param enable

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.16.1.1.3 Event

SCPI Command :

```
STATus:OPERation:BIT<BITNR>:[EVENT]
```

class EventCls

Event commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:[EVENT]
value: str = driver.status.operation.bit.event.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

event: No help available

6.16.1.1.4 Ntransition

SCPI Command :

```
STATus:OPERation:BIT<BITNR>:NTRansition
```

class NtransitionCls

Ntransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:NTRansition
value: str = driver.status.operation.bit.ntransition.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

ntransition: No help available

set(*ntransition: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:OPERation:BIT<BITNR>:NTRansition
driver.status.operation.bit.ntransition.set(ntransition = 'abc', bitNumberNull.
↳ repcap.BitNumberNull.Default)
```

No command help available

param ntransition

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.16.1.1.5 Ptransition**SCPI Command :**

```
STATus:OPERation:BIT<BITNR>:PTRansition
```

class PtransitionCls

Ptransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:OPERation:BIT<BITNR>:PTRansition
value: str = driver.status.operation.bit.ptransition.get(bitNumberNull = repcap.
↳ BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

ptransition: No help available

set(*ptransition: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:OPERation:BIT<BITNR>:PTRansition
driver.status.operation.bit.ptransition.set(ptransition = 'abc', bitNumberNull_
↳ = repcap.BitNumberNull.Default)
```

No command help available

param ptransition

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.16.2 Questionable**SCPI Commands :**

```
STATus:QUESTionable:CONDition
STATus:QUESTionable:ENABLE
STATus:QUESTionable:NTRansition
STATus:QUESTionable:PTRansition
STATus:QUESTionable:[EVENT]
```

class QuestionableCls

Questionable commands group definition. 10 total commands, 1 Subgroups, 5 group commands

get_condition() → str

```
# SCPI: STATUS:QUESTIONable:CONDition
value: str = driver.status.questionable.get_condition()
```

Queries the content of the CONDition part of the STATUS:QUESTIONable register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out since it indicates the current hardware status.

```
return
    condition: string
```

get_enable() → str

```
# SCPI: STATUS:QUESTIONable:ENABle
value: str = driver.status.questionable.get_enable()
```

Sets the bits of the ENABle part of the STATUS:QUESTIONable register. The enable part determines which events of the STATUS:EVENT part are enabled for the summary bit in the status byte. These events can be used for a service request. If a bit in the ENABle part is 1, and the corresponding EVENT bit is true, a positive transition occurs in the summary bit. This transition is reportet to the next higher level.

```
return
    enable: string
```

get_event() → str

```
# SCPI: STATUS:QUESTIONable:[EVENT]
value: str = driver.status.questionable.get_event()
```

Queries the content of the EVENT part of the method RsAreg.Status.Questionable.event register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

```
return
    value: No help available
```

get_ntransition() → str

```
# SCPI: STATUS:QUESTIONable:NTRansition
value: str = driver.status.questionable.get_ntransition()
```

Sets the bits of the NTRansition part of the STATUS:QUESTIONable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

```
return
    ntransition: string
```

get_ptransition() → str

```
# SCPI: STATUS:QUESTIONable:PTRansition
value: str = driver.status.questionable.get_ptransition()
```

Sets the bits of the PTRansition part of the STATUS:QUESTIONable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

```
return
    ptransition: string
```

set_condition(*condition: str*) → None

```
# SCPI: STATus:QUEStionable:CONDition
driver.status.questionable.set_condition(condition = 'abc')
```

Queries the content of the CONDition part of the STATus:QUEStionable register. This part contains information on the action currently being performed in the instrument. The content is not deleted after being read out since it indicates the current hardware status.

param condition
string

set_enable(*enable: str*) → None

```
# SCPI: STATus:QUEStionable:ENABle
driver.status.questionable.set_enable(enable = 'abc')
```

Sets the bits of the ENABle part of the STATus:QUEStionable register. The enable part determines which events of the STATus:EVENT part are enabled for the summary bit in the status byte. These events can be used for a service request. If a bit in the ENABle part is 1, and the corresponding EVENT bit is true, a positive transition occurs in the summary bit. This transition is reportet to the next higher level.

param enable
string

set_event(*value: str*) → None

```
# SCPI: STATus:QUEStionable:[EVENT]
driver.status.questionable.set_event(value = 'abc')
```

Queries the content of the EVENT part of the method RsAreg.Status.Questionable.event register. This part contains information on the actions performed in the instrument since the last readout. The content of the EVENT part is deleted after being read out.

param value
string

set_ntransition(*ntransition: str*) → None

```
# SCPI: STATus:QUEStionable:NTRansition
driver.status.questionable.set_ntransition(ntransition = 'abc')
```

Sets the bits of the NTRansition part of the STATus:QUEStionable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

param ntransition
string

set_ptransition(*ptransition: str*) → None

```
# SCPI: STATus:QUEStionable:PTRansition
driver.status.questionable.set_ptransition(ptransition = 'abc')
```

Sets the bits of the NTRansition part of the STATus:QUEStionable register. If a bit is set, a transition from 1 to 0 in the condition part causes an entry to be made in the EVENT part of the register.

param ptransition
string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.questionable.clone()
```

Subgroups

6.16.2.1 Bit<BitNumberNull>

RepCap Settings

```
# Range: Nr0 .. Nr15
rc = driver.status.questionable.bit.repcap_bitNumberNull_get()
driver.status.questionable.bit.repcap_bitNumberNull_set(repcap.BitNumberNull.Nr0)
```

class BitCls

Bit commands group definition. 5 total commands, 5 Subgroups, 0 group commands Repeated Capability: BitNumberNull, default value after init: BitNumberNull.Nr0

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.status.questionable.bit.clone()
```

Subgroups

6.16.2.1.1 Condition

SCPI Command :

```
STATUS:QUESTIONable:BIT<BITNR>:CONDition
```

class ConditionCls

Condition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATUS:QUESTIONable:BIT<BITNR>:CONDition
value: str = driver.status.questionable.bit.condition.get(bitNumberNull =
↳repcap.BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

condition: No help available

6.16.2.1.2 Enable

SCPI Command :

```
STATus:QUESTionable:BIT<BITNR>:ENABLE
```

class EnableCls

Enable commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:QUESTionable:BIT<BITNR>:ENABLE
value: str = driver.status.questionable.bit.enable.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

enable: No help available

set(*enable: str, bitNumberNull=BitNumberNull.Default*) → None

```
# SCPI: STATus:QUESTionable:BIT<BITNR>:ENABLE
driver.status.questionable.bit.enable.set(enable = 'abc', bitNumberNull =
↳repcap.BitNumberNull.Default)
```

No command help available

param enable

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.16.2.1.3 Event

SCPI Command :

```
STATus:QUESTionable:BIT<BITNR>:[EVENT]
```

class EventCls

Event commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(*bitNumberNull=BitNumberNull.Default*) → str

```
# SCPI: STATus:QUESTionable:BIT<BITNR>:[EVENT]
value: str = driver.status.questionable.bit.event.get(bitNumberNull = repcap.
↳BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return
event: No help available

6.16.2.1.4 Ntransition

SCPI Command :

```
STATUS:QUESTionable:BIT<BITNR>:NTRansition
```

class NtransitionCls

Ntransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATUS:QUESTionable:BIT<BITNR>:NTRansition
value: str = driver.status.questionable.bit.ntransition.get(bitNumberNull =
↳repcap.BitNumberNull.Default)
```

No command help available

param bitNumberNull
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return
ntransition: No help available

set(ntransition: str, bitNumberNull=BitNumberNull.Default) → None

```
# SCPI: STATUS:QUESTionable:BIT<BITNR>:NTRansition
driver.status.questionable.bit.ntransition.set(ntransition = 'abc',
↳bitNumberNull = repcap.BitNumberNull.Default)
```

No command help available

param ntransition
No help available

param bitNumberNull
optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.16.2.1.5 Ptransition

SCPI Command :

```
STATUS:QUESTionable:BIT<BITNR>:PTRansition
```

class PtransitionCls

Ptransition commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(bitNumberNull=BitNumberNull.Default) → str

```
# SCPI: STATUS:QUESTionable:BIT<BITNR>:PTRansition
value: str = driver.status.questionable.bit.ptransition.get(bitNumberNull =
↳repcap.BitNumberNull.Default)
```

No command help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

return

ptransition: No help available

set(ptransition: str, bitNumberNull=BitNumberNull.Default) → None

```
# SCPI: STATus:QUEStionable:BIT<BITNR>:PTRansition
driver.status.questionable.bit.ptransition.set(ptransition = 'abc',
↪ bitNumberNull = repcap.BitNumberNull.Default)
```

No command help available

param ptransition

No help available

param bitNumberNull

optional repeated capability selector. Default value: Nr0 (settable in the interface 'Bit')

6.16.3 Queue

SCPI Command :

STATus:QEEue:[NEXT]

class QueueCls

Queue commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_next() → str

```
# SCPI: STATus:QEEue:[NEXT]
value: str = driver.status.queue.get_next()
```

Queries the oldest entry in the error queue and then deletes it. Positive error numbers denote device-specific errors, and negative error numbers denote error messages defined by SCPI. If the error queue is empty, 0 ('No error') is returned. The command is identical to SYSTem:ERRor[:NEXT]?

return

next_py: string

6.17 System

SCPI Commands :

```
SYSTem:CRASH
SYSTem:DID
SYSTem:IMPort
SYSTem:IRESponse
SYSTem:LANGuage
SYSTem:NINformation
```

(continues on next page)

(continued from previous page)

```

SYSTEM:OREsponse
SYSTEM:OSYSem
SYSTEM:PRESet
SYSTEM:PRESet:ALL
SYSTEM:PRESet:BASE
SYSTEM:RCL
SYSTEM:RESet
SYSTEM:RESet:ALL
SYSTEM:RESet:BASE
SYSTEM:SAV
SYSTEM:SIMulation
SYSTEM:SRCat
SYSTEM:SREStore
SYSTEM:SRMode
SYSTEM:SRSel
SYSTEM:SSAVe
SYSTEM:TZONE
SYSTEM:UPTime
SYSTEM:VERSion
SYSTEM:WAIT

```

class SystemCls

System commands group definition. 182 total commands, 34 Subgroups, 26 group commands

get_did() → str

```

# SCPI: SYSem:DID
value: str = driver.system.get_did()

```

No command help available

```

return
    pseudo_string: No help available

```

get_iresponse() → str

```

# SCPI: SYSem:IREsponse
value: str = driver.system.get_iresponse()

```

Defines the user defined identification string for *IDN. Note: While working in an emulation mode, the instrument's specific command set is disabled, i.e. the SCPI command method RsAreg.System.iresponse is discarded.

```

return
    idn_response: string

```

get_language() → str

```

# SCPI: SYSem:LANGuage
value: str = driver.system.get_language()

```

Sets the remote control command set.

```

return
    language: string

```

get_ninformation() → str

```
# SCPI: SYSTem:NINformation
value: str = driver.system.get_ninformation()
```

Queries the oldest information message ('Error History > Level > Info') in the error/event queue.

```
return
    next_info: string
```

get_oresponse() → str

```
# SCPI: SYSTem:ORESponse
value: str = driver.system.get_oresponse()
```

Defines the user defined response string for *OPT. Note: While working in an emulation mode, the instrument's specific command set is disabled, i.e. the SCPI command method RsAreg.System.oresponse is discarded.

```
return
    oresponse: string
```

get_osystem() → str

```
# SCPI: SYSTem:OSYStem
value: str = driver.system.get_osystem()
```

Queries the operating system of the instrument.

```
return
    oper_system: string
```

get_simulation() → bool

```
# SCPI: SYSTem:SIMulation
value: bool = driver.system.get_simulation()
```

No command help available

```
return
    status: No help available
```

get_sr_cat() → List[str]

```
# SCPI: SYSTem:SRCat
value: List[str] = driver.system.get_sr_cat()
```

No command help available

```
return
    catalog: No help available
```

get_sr_mode() → RecScpiCmdMode

```
# SCPI: SYSTem:SRMode
value: enums.RecScpiCmdMode = driver.system.get_sr_mode()
```

No command help available

return
mode: No help available

get_sr_sel() → str

```
# SCPI: SYSTem:SRSe1
value: str = driver.system.get_sr_sel()
```

No command help available

return
filename: No help available

get_tzone() → str

```
# SCPI: SYSTem:TZONe
value: str = driver.system.get_tzone()
```

No command help available

return
pseudo_string: No help available

get_up_time() → str

```
# SCPI: SYSTem:UPTime
value: str = driver.system.get_up_time()
```

Queries the up time of the operating system.

return
up_time: 'ddd.hh:mm:ss'

get_version() → str

```
# SCPI: SYSTem:VERSiOn
value: str = driver.system.get_version()
```

Queries the SCPI version the instrument's command set complies with.

return
version: string

preset(pseudo_string: str) → None

```
# SCPI: SYSTem:PRESet
driver.system.preset(pseudo_string = 'abc')
```

INTRO_CMD_HELP: Triggers an instrument reset. It has the same effect as:

- The *RST command

:param pseudo_string: No help available

preset_all(pseudo_string: str) → None

```
# SCPI: SYSTem:PRESet:ALL
driver.system.preset_all(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

preset_base(pseudo_string: str) → None

```
# SCPI: SYSTem:PRESet:BASE
driver.system.preset_base(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

recall(path_name: str) → None

```
# SCPI: SYSTem:RCL
driver.system.recall(path_name = 'abc')
```

Loads a file with previously saved R&S AREG100A settings. Loads the selected file with previously saved R&S AREG100A settings from the default or the specified directory. Loaded are files with extension *.savreltxt.

param path_name

string

reset(pseudo_string: str) → None

```
# SCPI: SYSTem:RESet
driver.system.reset(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

reset_all(pseudo_string: str) → None

```
# SCPI: SYSTem:RESet:ALL
driver.system.reset_all(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

reset_base(pseudo_string: str) → None

```
# SCPI: SYSTem:RESet:BASE
driver.system.reset_base(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

save(*path_name: str*) → None

```
# SCPI: SYSTem:SAV
driver.system.save(path_name = 'abc')
```

Saves the current R&S AREG100A settings into a file with defined filename and into a specified directory. The file extension (*.savrltxt) is assigned automatically.

param path_name
string

set_crash(*test_scp_i_generic: float*) → None

```
# SCPI: SYSTem:CRASH
driver.system.set_crash(test_scp_i_generic = 1.0)
```

No command help available

param test_scp_i_generic
No help available

set_import_py(*filename: str*) → None

```
# SCPI: SYSTem:IMPort
driver.system.set_import_py(filename = 'abc')
```

No command help available

param filename
No help available

set_iresponse(*idn_response: str*) → None

```
# SCPI: SYSTem:IRESpOnse
driver.system.set_iresponse(idn_response = 'abc')
```

Defines the user defined identification string for *IDN. Note: While working in an emulation mode, the instrument's specific command set is disabled, i.e. the SCPI command method RsAreg.System.iresponse is discarded.

param idn_response
string

set_language(*language: str*) → None

```
# SCPI: SYSTem:LANGuage
driver.system.set_language(language = 'abc')
```

Sets the remote control command set.

param language
string

set_oresponse(*oresponse: str*) → None

```
# SCPI: SYSTem:ORESpOnse
driver.system.set_oresponse(oresponse = 'abc')
```

Defines the user defined response string for *OPT. Note: While working in an emulation mode, the instrument's specific command set is disabled, i.e. the SCPI command method RsAreg.System.oresponse is discarded.

param oresponse
string

set_sr_mode(mode: RecScpiCmdMode) → None

```
# SCPI: SYSTem:SRMode
driver.system.set_sr_mode(mode = enums.RecScpiCmdMode.AUTO)
```

No command help available

param mode
No help available

set_sr_sel(filename: str) → None

```
# SCPI: SYSTem:SRSel
driver.system.set_sr_sel(filename = 'abc')
```

No command help available

param filename
No help available

set_srestore(data_set: int) → None

```
# SCPI: SYSTem:SREStore
driver.system.set_srestore(data_set = 1)
```

No command help available

param data_set
No help available

set_ssave(data_set: int) → None

```
# SCPI: SYSTem:SSAVe
driver.system.set_ssave(data_set = 1)
```

No command help available

param data_set
No help available

set_tzone(pseudo_string: str) → None

```
# SCPI: SYSTem:TZONE
driver.system.set_tzone(pseudo_string = 'abc')
```

No command help available

param pseudo_string
No help available

set_wait(time_ms: int) → None

```
# SCPI: SYSTem:WAIT
driver.system.set_wait(time_ms = 1)
```

Delays the execution of the subsequent remote command by the specified time. This function is useful, for example to execute an SCPI sequence automatically but with a defined time delay between some commands. See ‘How to Assign Actions to the [User] Key’.

param time_ms
integer Wait time in ms Range: 0 to 10000

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.clone()
```

Subgroups

6.17.1 Beeper

SCPI Command :

```
SYSTem:BEEPer:STATe
```

class BeeperCls

Beeper commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:BEEPer:STATe
value: bool = driver.system.beeper.get_state()
```

No command help available

return
state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:BEEPer:STATe
driver.system.beeper.set_state(state = False)
```

No command help available

param state
No help available

6.17.2 Bios

SCPI Command :

```
SYSTem:BIOS:VERsion
```

class BiosCls

Bios commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:BIOS:VERsion
value: str = driver.system.bios.get_version()
```

Queries the BIOS version of the instrument.

```
return
    version: string
```

6.17.3 Communicate

class CommunicateCls

Communicate commands group definition. 23 total commands, 7 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.clone()
```

Subgroups

6.17.3.1 Gpib

SCPI Commands :

```
SYSTem:COMMunicate:GPIB:LTERminator
SYSTem:COMMunicate:GPIB:RESource
```

class GpibCls

Gpib commands group definition. 3 total commands, 1 Subgroups, 2 group commands

get_lterminator() → IecTermMode

```
# SCPI: SYSTem:COMMunicate:GPIB:LTERminator
value: enums.IecTermMode = driver.system.communicate.gpib.get_lterminator()
```

Sets the terminator recognition for remote control via GPIB interface.

```
return
    lterminator: STANDARD|EOI EOI Recognizes an LF (Line Feed) as the terminator only
    when it is sent with the line message EOI (End of Line) . This setting is recommended
```

particularly for binary block transmissions, as binary blocks may coincidentally contain a character with value LF (Line Feed) , although it is not determined as a terminator. STANdard Recognizes an LF (Line Feed) as the terminator regardless of whether it is sent with or without EOI.

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:GPIB:RESource
value: str = driver.system.communicate.gpib.get_resource()
```

Queries the visa resource string for remote control via the GPIB interface. To change the GPIB address, use the command method RsAreg.System.Communicate.Gpib.Self.address.

return
resource: string

set_lterminator(lterminator: IecTermMode) → None

```
# SCPI: SYSTem:COMMunicate:GPIB:LTERminator
driver.system.communicate.gpib.set_lterminator(lterminator = enums.IecTermMode.
↳EOI)
```

Sets the terminator recognition for remote control via GPIB interface.

param lterminator

STANdard| EOI EOI Recognizes an LF (Line Feed) as the terminator only when it is sent with the line message EOI (End of Line) . This setting is recommended particularly for binary block transmissions, as binary blocks may coincidentally contain a character with value LF (Line Feed) , although it is not determined as a terminator. STANdard Recognizes an LF (Line Feed) as the terminator regardless of whether it is sent with or without EOI.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.gpib.clone()
```

Subgroups

6.17.3.1.1 Self

SCPI Command :

```
SYSTem:COMMunicate:GPIB:[SELF]:ADDRess
```

class SelfCls

Self commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_address() → int

```
# SCPI: SYSTem:COMMunicate:GPIB:[SELF]:ADDRess
value: int = driver.system.communicate.gpib.self.get_address()
```

Sets the GPIB address.

return
address: integer Range: 0 to 30

set_address(address: int) → None

```
# SCPI: SYSTem:COMMunicate:GPIB:[SELF]:ADDRESS
driver.system.communicate.gpib.self.set_address(address = 1)
```

Sets the GPIB address.

param address
integer Range: 0 to 30

6.17.3.2 Hislip

SCPI Command :

```
SYSTem:COMMunicate:HISLip:RESource
```

class HislipCls

Hislip commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:HISLip:RESource
value: str = driver.system.communicate.hislip.get_resource()
```

Queries the VISA resource string. This string is used for remote control of the instrument with HiSLIP protocol.

return
resource: string

6.17.3.3 Network

SCPI Commands :

```
SYSTem:COMMunicate:NETWork:MACaddress
SYSTem:COMMunicate:NETWork:RESource
SYSTem:COMMunicate:NETWork:STATus
```

class NetworkCls

Network commands group definition. 12 total commands, 3 Subgroups, 3 group commands

get_mac_address() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:MACaddress
value: str = driver.system.communicate.network.get_mac_address()
```

Queries the MAC address of the network adapter. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg.System.Protect.State.set.

```

    return
        mac_address: string

```

```
get_resource() → str
```

```

# SCPI: SYSTem:COMMunicate:NETWork:RESource
value: str = driver.system.communicate.network.get_resource()

```

Queries the visa resource string for Ethernet instruments.

```

    return
        resource: string

```

```
get_status() → bool
```

```

# SCPI: SYSTem:COMMunicate:NETWork:STATus
value: bool = driver.system.communicate.network.get_status()

```

Queries the network configuration state.

```

    return
        state: 0| 1| OFF| ON

```

```
set_mac_address(mac_address: str) → None
```

```

# SCPI: SYSTem:COMMunicate:NETWork:MACaddress
driver.system.communicate.network.set_mac_address(mac_address = 'abc')

```

Queries the MAC address of the network adapter. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg.System.Protect.State.set.

```

    param mac_address
        string

```

Cloning the Group

```

# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.network.clone()

```

Subgroups

6.17.3.3.1 Common

SCPI Commands :

```

SYSTem:COMMunicate:NETWork:[COMMon]:DOWn
SYSTem:COMMunicate:NETWork:[COMMon]:HOSTname
SYSTem:COMMunicate:NETWork:[COMMon]:WORKgroup

```

```
class CommonCls
```

Common commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_domain() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[COMMON]:DOMain
value: str = driver.system.communicate.network.common.get_domain()
```

Determines the primary suffix of the network domain.

return
domain: string

get_hostname() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[COMMON]:HOSTname
value: str = driver.system.communicate.network.common.get_hostname()
```

Sets an individual hostname for the Automotive Radar Echo Generator. Note: We recommend that you do not change the hostname to avoid problems with the network connection. If you change the hostname, be sure to use a unique name. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg.System.Protect.State.set.

return
hostname: string

get_workgroup() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[COMMON]:WORKgroup
value: str = driver.system.communicate.network.common.get_workgroup()
```

Sets an individual workgroup name for the instrument.

return
workgroup: string

set_domain(domain: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[COMMON]:DOMain
driver.system.communicate.network.common.set_domain(domain = 'abc')
```

Determines the primary suffix of the network domain.

param domain
string

set_hostname(hostname: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[COMMON]:HOSTname
driver.system.communicate.network.common.set_hostname(hostname = 'abc')
```

Sets an individual hostname for the Automotive Radar Echo Generator. Note: We recommend that you do not change the hostname to avoid problems with the network connection. If you change the hostname, be sure to use a unique name. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg.System.Protect.State.set.

param hostname
string

set_workgroup(workgroup: str) → None


```
# SCPI: SYSTem:COMMunicate:NETWork:[COMMon]:WORKgroup
driver.system.communicate.network.common.set_workgroup(workgroup = 'abc')
```

Sets an individual workgroup name for the instrument.

param workgroup
string

6.17.3.3.2 IpAddress

SCPI Commands :

```
SYSTem:COMMunicate:NETWork:IPAdDress:MODE
SYSTem:COMMunicate:NETWork:[IPAdDress]:DNS
SYSTem:COMMunicate:NETWork:[IPAdDress]:GATeway
SYSTem:COMMunicate:NETWork:IPAdDress
```

class IpAddressCls

IpAddress commands group definition. 5 total commands, 1 Subgroups, 4 group commands

get_dns() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAdDress]:DNS
value: str = driver.system.communicate.network.ipAddress.get_dns()
```

Determines or queries the network DNS server to resolve the name.

return
dns: string

get_gateway() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAdDress]:GATeway
value: str = driver.system.communicate.network.ipAddress.get_gateway()
```

Sets the IP address of the default gateway.

return
gateway: string Range: 0.0.0.0 to ff.ff.ff.ff

get_mode() → NetMode

```
# SCPI: SYSTem:COMMunicate:NETWork:IPAdDress:MODE
value: enums.NetMode = driver.system.communicate.network.ipAddress.get_mode()
```

Selects manual or automatic setting of the IP address.

return
mode: AUTO| STATic

get_value() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:IPAdDress
value: str = driver.system.communicate.network.ipAddress.get_value()
```

Sets the IP address.

return
ip_address: string Range: 0.0.0.0. to ff.ff.ff.ff

set_dns(dns: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAddress]:DNS
driver.system.communicate.network.ipAddress.set_dns(dns = 'abc')
```

Determines or queries the network DNS server to resolve the name.

param dns
string

set_gateway(gateway: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAddress]:GATeway
driver.system.communicate.network.ipAddress.set_gateway(gateway = 'abc')
```

Sets the IP address of the default gateway.

param gateway
string Range: 0.0.0.0 to ff.ff.ff.ff

set_mode(mode: NetMode) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:IPAddress:MODE
driver.system.communicate.network.ipAddress.set_mode(mode = enums.NetMode.AUTO)
```

Selects manual or automatic setting of the IP address.

param mode
AUTO|STATic

set_value(ip_address: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:IPAddress
driver.system.communicate.network.ipAddress.set_value(ip_address = 'abc')
```

Sets the IP address.

param ip_address
string Range: 0.0.0.0. to ff.ff.ff.ff

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.network.ipAddress.clone()
```

Subgroups

6.17.3.3.2.1 Subnet

SCPI Command :

```
SYSTem:COMMunicate:NETWork:[IPAdDress]:SUBNet:MASK
```

class SubnetCls

Subnet commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_mask() → str

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAdDress]:SUBNet:MASK
value: str = driver.system.communicate.network.ipAddress.subnet.get_mask()
```

Sets the subnet mask.

```
return
    mask: string
```

set_mask(mask: str) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:[IPAdDress]:SUBNet:MASK
driver.system.communicate.network.ipAddress.subnet.set_mask(mask = 'abc')
```

Sets the subnet mask.

```
param mask
    string
```

6.17.3.3.3 Restart

SCPI Command :

```
SYSTem:COMMunicate:NETWork:REStArt
```

class RestartCls

Restart commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:COMMunicate:NETWork:REStArt
driver.system.communicate.network.restart.set()
```

Restarts the network.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:COMMunicate:NETWork:REStArt
driver.system.communicate.network.restart.set_with_opc()
```

Restarts the network.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.3.4 Scpi

class ScpiCls

Scpi commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.communicate.scpi.clone()
```

Subgroups

6.17.3.4.1 Ethernet

SCPI Command :

```
SYSTem:COMMunicate:SCPI:ETHernet:[ACTive]
```

class EthernetCls

Ethernet commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_active() → str

```
# SCPI: SYSTem:COMMunicate:SCPI:ETHernet:[ACTive]
value: str = driver.system.communicate.scpi.ethernet.get_active()
```

No command help available

return

active_connection: No help available

6.17.3.5 Serial

SCPI Commands :

```
SYSTem:COMMunicate:SERial:BAUD
SYSTem:COMMunicate:SERial:PARity
SYSTem:COMMunicate:SERial:RESource
SYSTem:COMMunicate:SERial:SBITs
```

class SerialCls

Serial commands group definition. 4 total commands, 0 Subgroups, 4 group commands

get_baud() → Rs232BdRate

```
# SCPI: SYSTem:COMMunicate:SERIal:BAUD
value: enums.Rs232BdRate = driver.system.communicate.serial.get_baud()
```

Defines the baudrate for the serial remote control interface.

```
return
    baud: 2400| 4800| 9600| 19200| 38400| 57600| 115200
```

get_parity() → Parity

```
# SCPI: SYSTem:COMMunicate:SERIal:PARity
value: enums.Parity = driver.system.communicate.serial.get_parity()
```

Enters the parity for the serial remote control interface.

```
return
    parity: NONE| ODD| EVEN
```

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:SERIal:RESource
value: str = driver.system.communicate.serial.get_resource()
```

Queries the visa resource string for the serial remote control interface. This string is used for remote control of the instrument.

```
return
    resource: string
```

get_sbits() → Rs232StopBits

```
# SCPI: SYSTem:COMMunicate:SERIal:SBITS
value: enums.Rs232StopBits = driver.system.communicate.serial.get_sbits()
```

Defines the number of stop bits for the serial remote control interface.

```
return
    sbits: 1| 2
```

set_baud(baud: Rs232BdRate) → None

```
# SCPI: SYSTem:COMMunicate:SERIal:BAUD
driver.system.communicate.serial.set_baud(baud = enums.Rs232BdRate._115200)
```

Defines the baudrate for the serial remote control interface.

```
param baud
    2400| 4800| 9600| 19200| 38400| 57600| 115200
```

set_parity(parity: Parity) → None

```
# SCPI: SYSTem:COMMunicate:SERIal:PARity
driver.system.communicate.serial.set_parity(parity = enums.Parity.EVEN)
```

Enters the parity for the serial remote control interface.

```
param parity
    NONE| ODD| EVEN
```

set_sbits(sbits: Rs232StopBits) → None

```
# SCPI: SYSTem:COMMunicate:SErial:SBITs
driver.system.communicate.serial.set_sbits(sbits = enums.Rs232StopBits._1)
```

Defines the number of stop bits for the serial remote control interface.

param sbits
1| 2

6.17.3.6 Socket

SCPI Command :

```
SYSTem:COMMunicate:SOCKet:RESource
```

class SocketCls

Socket commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:SOCKet:RESource
value: str = driver.system.communicate.socket.get_resource()
```

Queries the visa resource string for remote control via LAN interface, using TCP/IP socket protocol.

return
resource: string

6.17.3.7 Usb

SCPI Command :

```
SYSTem:COMMunicate:USB:RESource
```

class UsbCls

Usb commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_resource() → str

```
# SCPI: SYSTem:COMMunicate:USB:RESource
value: str = driver.system.communicate.usb.get_resource()
```

Queries the visa resource string for remote control via the USB interface.

return
resource: string

6.17.4 Date

SCPI Commands :

```
SYSTem:DATE
SYSTem:DATE:LOCa1
SYSTem:DATE:UTC
```

class DateCls

Date commands group definition. 3 total commands, 0 Subgroups, 3 group commands

class DateStruct

Response structure. Fields:

- Year: List[int]: integer
- Month: int: integer Range: 1 to 12
- Day: int: integer Range: 1 to 31

get() → DateStruct

```
# SCPI: SYSTem:DATE
value: DateStruct = driver.system.date.get()
```

Queries or sets the date for the instrument-internal calendar. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg.System.Protect.State.set.

return

structure: for return value, see the help for DateStruct structure arguments.

get_local() → str

```
# SCPI: SYSTem:DATE:LOCa1
value: str = driver.system.date.get_local()
```

No command help available

return

pseudo_string: No help available

get_utc() → str

```
# SCPI: SYSTem:DATE:UTC
value: str = driver.system.date.get_utc()
```

No command help available

return

pseudo_string: No help available

set(year: List[int], month: int, day: int) → None

```
# SCPI: SYSTem:DATE
driver.system.date.set(year = [1, 2, 3], month = 1, day = 1)
```

Queries or sets the date for the instrument-internal calendar. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg.System.Protect.State.set.

param year

integer

param month

integer Range: 1 to 12

param day

integer Range: 1 to 31

set_local(*pseudo_string*: str) → None

```
# SCPI: SYSTem:DATE:LOCa1
driver.system.date.set_local(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

set_utc(*pseudo_string*: str) → None

```
# SCPI: SYSTem:DATE:UTC
driver.system.date.set_utc(pseudo_string = 'abc')
```

No command help available

param pseudo_string

No help available

6.17.5 Device

SCPI Command :

```
SYSTem:DEVIce:ID
```

class DeviceCls

Device commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_id() → str

```
# SCPI: SYSTem:DEVIce:ID
value: str = driver.system.device.get_id()
```

No command help available

return

pseudo_string: No help available

6.17.6 DeviceFootprint

SCPI Command :

```
SYSTem:DFPRint
```

class DeviceFootprintCls

DeviceFootprint commands group definition. 3 total commands, 1 Subgroups, 1 group commands

get() → str

```
# SCPI: SYSTem:DFPRint
value: str = driver.system.deviceFootprint.get()
```

Queries the device footprint of the instrument. The retrieved information is in machine-readable form suitable for automatic further processing.

return

device_footprint: string Information on the instrument type, device identification and details on the installed FW version, hardware and software options.

set(directory: str) → None

```
# SCPI: SYSTem:DFPRint
driver.system.deviceFootprint.set(directory = 'abc')
```

Queries the device footprint of the instrument. The retrieved information is in machine-readable form suitable for automatic further processing.

param directory

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.deviceFootprint.clone()
```

Subgroups

6.17.6.1 History

SCPI Commands :

```
SYSTem:DFPRint:HISTory:COUNT
SYSTem:DFPRint:HISTory:ENTRY
```

class HistoryCls

History commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_count() → str

```
# SCPI: SYSTem:DFPRint:HISTory:COUNT
value: str = driver.system.deviceFootprint.history.get_count()
```

No command help available

return
pseudo_string: No help available

get_entry() → str

```
# SCPI: SYSTem:DFPrint:HISTory:ENTry
value: str = driver.system.deviceFootprint.history.get_entry()
```

No command help available

return
pseudo_string: No help available

6.17.7 Dexchange

SCPI Commands :

```
SYSTem:DEXChange:CATalog
SYSTem:DEXChange:DEBug
SYSTem:DEXChange:DELeTe
SYSTem:DEXChange:FORMat
SYSTem:DEXChange:SElect
```

class DexchangeCls

Dexchange commands group definition. 12 total commands, 3 Subgroups, 5 group commands

delete(filename: str) → None

```
# SCPI: SYSTem:DEXChange:DELeTe
driver.system.dexchange.delete(filename = 'abc')
```

No command help available

param filename
No help available

get_catalog() → List[str]

```
# SCPI: SYSTem:DEXChange:CATalog
value: List[str] = driver.system.dexchange.get_catalog()
```

No command help available

return
catalog: No help available

get_debug() → bool

```
# SCPI: SYSTem:DEXChange:DEBug
value: bool = driver.system.dexchange.get_debug()
```

No command help available

return
debug: No help available

get_format_py() → DevExpFormat

```
# SCPI: SYSTem:DEXChange:FORMat
value: enums.DevExpFormat = driver.system.dexchange.get_format_py()
```

No command help available

```
return
    format_py: No help available
```

get_select() → str

```
# SCPI: SYSTem:DEXChange:SElect
value: str = driver.system.dexchange.get_select()
```

No command help available

```
return
    filename: No help available
```

set_debug(debug: bool) → None

```
# SCPI: SYSTem:DEXChange:DEBug
driver.system.dexchange.set_debug(debug = False)
```

No command help available

```
param debug
    No help available
```

set_format_py(format_py: DevExpFormat) → None

```
# SCPI: SYSTem:DEXChange:FORMat
driver.system.dexchange.set_format_py(format_py = enums.DevExpFormat.
    CGPREDEFINED)
```

No command help available

```
param format_py
    No help available
```

set_select(filename: str) → None

```
# SCPI: SYSTem:DEXChange:SElect
driver.system.dexchange.set_select(filename = 'abc')
```

No command help available

```
param filename
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.dexchange.clone()
```

Subgroups

6.17.7.1 Execute

SCPI Command :

```
SYSTem:DEXChange:EXECute
```

class ExecuteCls

Execute commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:DEXChange:EXECute
driver.system.dexchange.execute.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:DEXChange:EXECute
driver.system.dexchange.execute.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.7.2 Template

class TemplateCls

Template commands group definition. 5 total commands, 2 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.dexchange.template.clone()
```

Subgroups

6.17.7.2.1 Predefined

SCPI Commands :

```
SYSTem:DEXChange:TEMPlate:PREDefined:CATalog
SYSTem:DEXChange:TEMPlate:PREDefined:SElect
```

class PredefinedCls

Predefined commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: SYSTem:DEXChange:TEMPlate:PREDefined:CATalog
value: List[str] = driver.system.dexchange.template.predefined.get_catalog()
```

No command help available

```
return
    catalog: No help available
```

get_select() → str

```
# SCPI: SYSTem:DEXChange:TEMPlate:PREDefined:SElect
value: str = driver.system.dexchange.template.predefined.get_select()
```

No command help available

```
return
    filename: No help available
```

set_select(filename: str) → None

```
# SCPI: SYSTem:DEXChange:TEMPlate:PREDefined:SElect
driver.system.dexchange.template.predefined.set_select(filename = 'abc')
```

No command help available

```
param filename
    No help available
```

6.17.7.2.2 User

SCPI Commands :

```
SYSTem:DEXChange:TEMPlate:USER:CATalog
SYSTem:DEXChange:TEMPlate:USER:DELeTe
SYSTem:DEXChange:TEMPlate:USER:SElect
```

class UserCls

User commands group definition. 3 total commands, 0 Subgroups, 3 group commands

delete(filename: str) → None

```
# SCPI: SYSTem:DEXChange:TEMPlate:USER:DELeTe
driver.system.dexchange.template.user.delete(filename = 'abc')
```

No command help available

param filename

No help available

get_catalog() → List[str]

```
# SCPI: SYSTem:DEXChange:TEMPlate:USER:CATalog
value: List[str] = driver.system.dexchange.template.user.get_catalog()
```

No command help available

return

catalog: No help available

get_select() → str

```
# SCPI: SYSTem:DEXChange:TEMPlate:USER:SELeCt
value: str = driver.system.dexchange.template.user.get_select()
```

No command help available

return

filename: No help available

set_select(filename: str) → None

```
# SCPI: SYSTem:DEXChange:TEMPlate:USER:SELeCt
driver.system.dexchange.template.user.set_select(filename = 'abc')
```

No command help available

param filename

No help available

6.17.7.3 Transaction

SCPI Command :

```
SYSTem:DEXChange:TRANsaction:STATe
```

class TransactionCls

Transaction commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:DEXChange:TRANsaction:STATe
value: bool = driver.system.dexchange.transaction.get_state()
```

No command help available

return
state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:DEXChange:TRANsaction:STATe
driver.system.dexchange.transaction.set_state(state = False)
```

No command help available

param state
No help available

6.17.8 Error

SCPI Commands :

```
SYSTem:ERRor:ALL
SYSTem:ERRor:COUNt
SYSTem:ERRor:STATic
```

class ErrorCls

Error commands group definition. 7 total commands, 2 Subgroups, 3 group commands

get_all() → str

```
# SCPI: SYSTem:ERRor:ALL
value: str = driver.system.error.get_all()
```

Queries the error/event queue for all unread items and removes them from the queue.

return
all_py: string Error/event_number,'Error/event_description[:Device-dependent info]'
A comma separated list of error number and a short description of the error in FIFO order. If the queue is empty, the response is 0,'No error' Positive error numbers are instrument-dependent. Negative error numbers are reserved by the SCPI standard. Volatile errors are reported once, at the time they appear. Identical errors are reported repeatedly only if the original error has already been retrieved from (and hence not any more present in) the error queue.

get_count() → str

```
# SCPI: SYSTem:ERRor:COUNt
value: str = driver.system.error.get_count()
```

Queries the number of entries in the error queue.

return
count: integer 0 The error queue is empty.

get_static() → str

```
# SCPI: SYSTem:ERRor:STATic
value: str = driver.system.error.get_static()
```

Returns a list of all errors existing at the time when the query is started. This list corresponds to the display on the info page under manual control.

return
static_errors: string

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.error.clone()
```

Subgroups

6.17.8.1 Code

SCPI Commands :

```
SYSTem:ERRor:CODE:ALL
SYSTem:ERRor:CODE:[NEXT]
```

class CodeCls

Code commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_all() → str

```
# SCPI: SYSTem:ERRor:CODE:ALL
value: str = driver.system.error.code.get_all()
```

Queries the error numbers of all entries in the error queue and then deletes them.

return
all_py: string Returns the error numbers. To retrieve the entire error text, send the command method RsAreg.System.Error.all. 0 'No error', i.e. the error queue is empty Positive value Positive error numbers denote device-specific errors Negative value Negative error numbers denote error messages defined by SCPI.

get_next() → str

```
# SCPI: SYSTem:ERRor:CODE:[NEXT]
value: str = driver.system.error.code.get_next()
```

Queries the error number of the oldest entry in the error queue and then deletes it.

return
next_py: string Returns the error number. To retrieve the entire error text, send the command method RsAreg.System.Error.all. 0 'No error', i.e. the error queue is empty Positive value Positive error numbers denote device-specific errors Negative value Negative error numbers denote error messages defined by SCPI.

6.17.8.2 History

SCPI Commands :

```
SYSTem:ERRor:HISTory:CLEar
SYSTem:ERRor:HISTory
```

class HistoryCls

History commands group definition. 2 total commands, 0 Subgroups, 2 group commands

clear() → None

```
# SCPI: SYSTem:ERRor:HISTory:CLEar
driver.system.error.history.clear()
```

Clears the error history.

clear_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:ERRor:HISTory:CLEar
driver.system.error.history.clear_with_opc()
```

Clears the error history.

Same as clear, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_value() → str

```
# SCPI: SYSTem:ERRor:HISTory
value: str = driver.system.error.history.get_value()
```

No command help available

return

error_history: No help available

6.17.9 ExtDevices

class ExtDevicesCls

ExtDevices commands group definition. 5 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.extDevices.clone()
```

Subgroups

6.17.9.1 Update

SCPI Command :

```
SYSTem:EXTDevices:UPDate
```

class UpdateCls

Update commands group definition. 5 total commands, 3 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:EXTDevices:UPDate
driver.system.extDevices.update.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:EXTDevices:UPDate
driver.system.extDevices.update.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.extDevices.update.clone()
```

Subgroups

6.17.9.1.1 Check

SCPI Command :

```
SYSTem:EXTDevices:UPDate:CHECK
```

class CheckCls

Check commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:EXTDevices:UPDate:CHECK
driver.system.extDevices.update.check.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:EXTDevices:UPDate:CHECK
driver.system.extDevices.update.check.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.9.1.2 Needed**SCPI Command :**

```
SYSTem:EXTDevices:UPDate:NEEDed:[STATe]
```

class NeededCls

Needed commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:EXTDevices:UPDate:NEEDed:[STATe]
value: bool = driver.system.extDevices.update.needed.get_state()
```

No command help available

return

update_needed: No help available

6.17.9.1.3 Tselected**SCPI Commands :**

```
SYSTem:EXTDevices:UPDate:TSElected:CATalog
SYSTem:EXTDevices:UPDate:TSElected:STEP
```

class TselectedCls

Tselected commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → str

```
# SCPI: SYSTem:EXTDevices:UPDate:TSElected:CATalog
value: str = driver.system.extDevices.update.tselected.get_catalog()
```

No command help available

```
return
    catalog: No help available
```

get_step() → str

```
# SCPI: SYSTem:EXTDevices:UPDate:TSElected:STEP
value: str = driver.system.extDevices.update.tselected.get_step()
```

No command help available

```
return
    sel_string: No help available
```

set_step(sel_string: str) → None

```
# SCPI: SYSTem:EXTDevices:UPDate:TSElected:STEP
driver.system.extDevices.update.tselected.set_step(sel_string = 'abc')
```

No command help available

```
param sel_string
    No help available
```

6.17.10 Fpreset

SCPI Command :

```
SYSTem:FPRreset
```

class FpresetCls

Fpreset commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:FPRreset
driver.system.fpreset.set()
```

Triggers an instrument reset to the original state of delivery.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:FPRreset
driver.system.fpreset.set_with_opc()
```

Triggers an instrument reset to the original state of delivery.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.11 Generic

SCPI Command :

```
SYSTem:GENeric:MSG
```

class GenericCls

Generic commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_msg() → str

```
# SCPI: SYSTem:GENeric:MSG
value: str = driver.system.generic.get_msg()
```

No command help available

return

generic_message: No help available

set_msg(generic_message: str) → None

```
# SCPI: SYSTem:GENeric:MSG
driver.system.generic.set_msg(generic_message = 'abc')
```

No command help available

param generic_message

No help available

6.17.12 Help

SCPI Commands :

```
SYSTem:HELP:EXPort
SYSTem:HELP:HEADers
```

class HelpCls

Help commands group definition. 4 total commands, 1 Subgroups, 2 group commands

export() → None

```
# SCPI: SYSTem:HELP:EXPort
driver.system.help.export()
```

Saves the online help as zip archive in the user directory.

export_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:HELP:EXPort
driver.system.help.export_with_opc()
```

Saves the online help as zip archive in the user directory.

Same as export, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param `opc_timeout_ms`

Maximum time to wait in milliseconds, valid only for this call.

get_headers() → str

```
# SCPI: SYSTem:HELP:HEADers
value: str = driver.system.help.get_headers()
```

No command help available

return

headers: No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.help.clone()
```

Subgroups

6.17.12.1 Syntax

SCPI Commands :

```
SYSTem:HELP:SYNTAX:ALL
SYSTem:HELP:SYNTAX
```

class `SyntaxCls`

Syntax commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_all() → str

```
# SCPI: SYSTem:HELP:SYNTAX:ALL
value: str = driver.system.help.syntax.get_all()
```

No command help available

return

pseudo_string: No help available

get_value() → str

```
# SCPI: SYSTem:HELP:SYNTAX
value: str = driver.system.help.syntax.get_value()
```

No command help available

return

pseudo_string: No help available

6.17.13 Identification

SCPI Commands :

```
SYSTem:IDENtification:PRESet
SYSTem:IDENtification
```

class IdentificationCls

Identification commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_value() → IecDevId

```
# SCPI: SYSTem:IDENtification
value: enums.IecDevId = driver.system.identification.get_value()
```

Selects the mode to determine the ‘IDN String’ and the ‘OPT String’ for the instrument, selected with command method RsAreg.System.language. Note: While working in an emulation mode, the R&S AREG100A specific command set is disabled, that is, the SCPI command method RsAreg.System.Identification.value is discarded.

return

identification: AUTO| USER AUTO Automatically determines the strings. USER User-defined strings can be selected.

preset() → None

```
# SCPI: SYSTem:IDENtification:PRESet
driver.system.identification.preset()
```

Sets the *IDN and *OPT strings in user defined mode to default values.

preset_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:IDENtification:PRESet
driver.system.identification.preset_with_opc()
```

Sets the *IDN and *OPT strings in user defined mode to default values.

Same as preset, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

set_value(identification: IecDevId) → None

```
# SCPI: SYSTem:IDENtification
driver.system.identification.set_value(identification = enums.IecDevId.AUTO)
```

Selects the mode to determine the ‘IDN String’ and the ‘OPT String’ for the instrument, selected with command method RsAreg.System.language. Note: While working in an emulation mode, the R&S AREG100A specific command set is disabled, that is, the SCPI command method RsAreg.System.Identification.value is discarded.

param identification

AUTO| USER AUTO Automatically determines the strings. USER User-defined strings can be selected.

6.17.14 Information

SCPI Command :

```
SYSTem:INformation:SR
```

class InformationCls

Information commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_sr() → str

```
# SCPI: SYSTem:INformation:SR
value: str = driver.system.information.get_sr()
```

No command help available

return
sr_info: No help available

set_sr(sr_info: str) → None

```
# SCPI: SYSTem:INformation:SR
driver.system.information.set_sr(sr_info = 'abc')
```

No command help available

param sr_info
No help available

6.17.15 Linux

class LinuxCls

Linux commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.linux.clone()
```

Subgroups

6.17.15.1 Kernel

SCPI Command :

```
SYSTem:LINux:KERNel:VERSion
```

class KernelCls

Kernel commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:LINux:KERNel:VERsion
value: str = driver.system.linux.kernel.get_version()
```

No command help available

```
return
    version: No help available
```

6.17.16 Lock

SCPI Command :

```
SYSTem:LOCK:TIMEout
```

class LockCls

Lock commands group definition. 10 total commands, 5 Subgroups, 1 group commands

get_timeout() → int

```
# SCPI: SYSTem:LOCK:TIMEout
value: int = driver.system.lock.get_timeout()
```

No command help available

```
return
    time_ms: No help available
```

set_timeout(time_ms: int) → None

```
# SCPI: SYSTem:LOCK:TIMEout
driver.system.lock.set_timeout(time_ms = 1)
```

No command help available

```
param time_ms
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.lock.clone()
```

Subgroups

6.17.16.1 Name

SCPI Commands :

```
SYSTem:LOCK:NAME:DETAiled
SYSTem:LOCK:NAME
```

class NameCls

Name commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_detailed() → str

```
# SCPI: SYSTem:LOCK:NAME:DETAiled
value: str = driver.system.lock.name.get_detailed()
```

No command help available

```
return
    details: No help available
```

get_value() → str

```
# SCPI: SYSTem:LOCK:NAME
value: str = driver.system.lock.name.get_value()
```

No command help available

```
return
    name: No help available
```

6.17.16.2 Owner

SCPI Commands :

```
SYSTem:LOCK:OWNer:DETAiled
SYSTem:LOCK:OWNer
```

class OwnerCls

Owner commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_detailed() → str

```
# SCPI: SYSTem:LOCK:OWNer:DETAiled
value: str = driver.system.lock.owner.get_detailed()
```

No command help available

```
return
    details: No help available
```

get_value() → str

```
# SCPI: SYSTem:LOCK:OWNeR
value: str = driver.system.lock.owner.get_value()
```

Queries the sessions that have locked the instrument currently. If an exclusive lock is set, the query returns the owner of this exclusive lock, otherwise it returns NONE.

```
return
    owner: string
```

6.17.16.3 Release

SCPI Commands :

```
SYSTem:LOCK:RELease:ALL
SYSTem:LOCK:RELease
```

class ReleaseCls

Release commands group definition. 2 total commands, 0 Subgroups, 2 group commands

set_all(pseudo_string: str) → None

```
# SCPI: SYSTem:LOCK:RELease:ALL
driver.system.lock.release.set_all(pseudo_string = 'abc')
```

Revokes the exclusive access to the instrument.

```
param pseudo_string
    No help available
```

set_value(pseudo_string: str) → None

```
# SCPI: SYSTem:LOCK:RELease
driver.system.lock.release.set_value(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
    No help available
```

6.17.16.4 Request

SCPI Command :

```
SYSTem:LOCK:REQuest:[EXCLusive]
```

class RequestCls

Request commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_exclusive() → int

```
# SCPI: SYSTem:LOCK:REQuest:[EXCLusive]
value: int = driver.system.lock.request.get_exclusive()
```

Queries whether a lock for exclusive access to the instrument via ethernet exists. If successful, the query returns a 1, otherwise 0.

return
success: integer

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.lock.request.clone()
```

Subgroups

6.17.16.4.1 Shared

SCPI Command :

```
SYSTem:LOCK:REQuest:SHARed
```

class SharedCls

Shared commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(name: str, timeout_ms: int) → int

```
# SCPI: SYSTem:LOCK:REQuest:SHARed
value: int = driver.system.lock.request.shared.get(name = 'abc', timeout_ms = 1)
```

No command help available

param name
No help available

param timeout_ms
No help available

return
success: No help available

6.17.16.5 Shared

SCPI Command :

```
SYSTem:LOCK:SHARed:STRing
```

class SharedCls

Shared commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_string() → str

```
# SCPI: SYSTem:LOCK:SHARed:STRing
value: str = driver.system.lock.shared.get_string()
```

No command help available

```

return
    string: No help available

```

6.17.17 MassMemory

class MassMemoryCls

MassMemory commands group definition. 2 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```

# Create a clone of the original group, that exists independently
group2 = driver.system.massMemory.clone()

```

Subgroups

6.17.17.1 Path

SCPI Commands :

```

SYSTEM:MMEMory:PATH
SYSTEM:MMEMory:PATH:USER

```

class PathCls

Path commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get(*path_type: str*) → str

```

# SCPI: SYSTEM:MMEMory:PATH
value: str = driver.system.massMemory.path.get(path_type = 'abc')

```

No command help available

```

param path_type
    No help available

```

```

return
    path: No help available

```

get_user() → str

```

# SCPI: SYSTEM:MMEMory:PATH:USER
value: str = driver.system.massMemory.path.get_user()

```

Queries the user directory, that means the directory the R&S AREG100A stores user files on.

```

return
    path_user: string

```

6.17.18 Ntp

SCPI Command :

```
SYSTem:NTP:HOSTname
```

class NtpCls

Ntp commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_hostname() → str

```
# SCPI: SYSTem:NTP:HOSTname
value: str = driver.system.ntp.get_hostname()
```

Sets the address of the NTP server. You can enter the IP address, or the hostname of the time server, or even set up an own vendor zone. See the Internet for more information on NTP.

return
ntp_name: string

set_hostname(ntp_name: str) → None

```
# SCPI: SYSTem:NTP:HOSTname
driver.system.ntp.set_hostname(ntp_name = 'abc')
```

Sets the address of the NTP server. You can enter the IP address, or the hostname of the time server, or even set up an own vendor zone. See the Internet for more information on NTP.

param ntp_name
string

6.17.19 Package

class PackageCls

Package commands group definition. 3 total commands, 3 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.package.clone()
```

Subgroups

6.17.19.1 ChartDisplay

SCPI Command :

```
SYSTem:PACKage:CHARtdisplay:VERSion
```

class ChartDisplayCls

ChartDisplay commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:PACKage:CHARTdisplay:VERsion
value: str = driver.system.package.chartDisplay.get_version()
```

No command help available

```
return
    version: No help available
```

6.17.19.2 GuiFramework

SCPI Command :

```
SYSTem:PACKage:GUIFramework:VERsion
```

class GuiFrameworkCls

GuiFramework commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:PACKage:GUIFramework:VERsion
value: str = driver.system.package.guiFramework.get_version()
```

No command help available

```
return
    version: No help available
```

6.17.19.3 Qt

SCPI Command :

```
SYSTem:PACKage:QT:VERsion
```

class QtCls

Qt commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_version() → str

```
# SCPI: SYSTem:PACKage:QT:VERsion
value: str = driver.system.package.qt.get_version()
```

No command help available

```
return
    version: No help available
```

6.17.20 PciFpga

class PciFpgaCls

PciFpga commands group definition. 5 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.pciFpga.clone()
```

Subgroups

6.17.20.1 Update

SCPI Command :

```
SYSTem:PCIFpga:UPDate
```

class UpdateCls

Update commands group definition. 5 total commands, 3 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:PCIFpga:UPDate
driver.system.pciFpga.update.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:PCIFpga:UPDate
driver.system.pciFpga.update.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.pciFpga.update.clone()
```


Subgroups

6.17.20.1.1 Check

SCPI Command :

```
SYSTem:PCIFpga:UPDate:CHECK
```

class CheckCls

Check commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:PCIFpga:UPDate:CHECK
driver.system.pciFpga.update.check.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:PCIFpga:UPDate:CHECK
driver.system.pciFpga.update.check.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.20.1.2 Needed

SCPI Command :

```
SYSTem:PCIFpga:UPDate:NEEDED:[STATe]
```

class NeededCls

Needed commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:PCIFpga:UPDate:NEEDED:[STATe]
value: bool = driver.system.pciFpga.update.needed.get_state()
```

No command help available

return

update_needed: No help available

6.17.20.1.3 Tselected

SCPI Commands :

```
SYSTem:PCIFpga:UPDate:TSElected:CATalog  
SYSTem:PCIFpga:UPDate:TSElected:STEP
```

class TselectedCls

Tselected commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → str

```
# SCPI: SYSTem:PCIFpga:UPDate:TSElected:CATalog  
value: str = driver.system.pciFpga.update.tselected.get_catalog()
```

No command help available

```
return  
    catalog: No help available
```

get_step() → str

```
# SCPI: SYSTem:PCIFpga:UPDate:TSElected:STEP  
value: str = driver.system.pciFpga.update.tselected.get_step()
```

No command help available

```
return  
    sel_string: No help available
```

set_step(sel_string: str) → None

```
# SCPI: SYSTem:PCIFpga:UPDate:TSElected:STEP  
driver.system.pciFpga.update.tselected.set_step(sel_string = 'abc')
```

No command help available

```
param sel_string  
    No help available
```

6.17.21 Profiling

SCPI Command :

```
SYSTem:PROFiling:STATe
```

class ProfilingCls

Profiling commands group definition. 18 total commands, 6 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:PROFiling:STATe  
value: bool = driver.system.profiling.get_state()
```

No command help available

return

state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:STaTe
driver.system.profiling.set_state(state = False)
```

No command help available

param state

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.profiling.clone()
```

Subgroups

6.17.21.1 HwAccess

SCPI Commands :

```
SYSTem:PROFiling:HWACcess:DESCription
SYSTem:PROFiling:HWACcess:PDURation
SYSTem:PROFiling:HWACcess:STaTe
```

class HwAccessCls

HwAccess commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_description() → str

```
# SCPI: SYSTem:PROFiling:HWACcess:DESCription
value: str = driver.system.profiling.hwAccess.get_description()
```

No command help available

return

description: No help available

get_pduration() → int

```
# SCPI: SYSTem:PROFiling:HWACcess:PDURation
value: int = driver.system.profiling.hwAccess.get_pduration()
```

No command help available

return

duration_us: No help available

get_state() → bool

```
# SCPI: SYSTem:PROFiling:HWACcess:STaTe
value: bool = driver.system.profiling.hwAccess.get_state()
```

No command help available

```
return
    state: No help available
```

set_pduration(duration_us: int) → None

```
# SCPI: SYSTem:PROFiling:HWACcess:PDURation
driver.system.profiling.hwAccess.set_pduration(duration_us = 1)
```

No command help available

```
param duration_us
    No help available
```

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:HWACcess:STaTe
driver.system.profiling.hwAccess.set_state(state = False)
```

No command help available

```
param state
    No help available
```

6.17.21.2 Logging

SCPI Command :

```
SYSTem:PROFiling:LOGGing:STaTe
```

class LoggingCls

Logging commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:PROFiling:LOGGing:STaTe
value: bool = driver.system.profiling.logging.get_state()
```

No command help available

```
return
    state: No help available
```

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:LOGGing:STaTe
driver.system.profiling.logging.set_state(state = False)
```

No command help available

```
param state
    No help available
```

6.17.21.3 Module

SCPI Commands :

```
SYSTem:PROFiling:MODule:CATalog
SYSTem:PROFiling:MODule:STATe
```

class ModuleCls

Module commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: SYSTem:PROFiling:MODule:CATalog
value: List[str] = driver.system.profiling.module.get_catalog()
```

No command help available

```
return
    catalog: No help available
```

get_state() → bool

```
# SCPI: SYSTem:PROFiling:MODule:STATe
value: bool = driver.system.profiling.module.get_state()
```

No command help available

```
return
    state: No help available
```

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:MODule:STATe
driver.system.profiling.module.set_state(state = False)
```

No command help available

```
param state
    No help available
```

6.17.21.4 Record

SCPI Commands :

```
SYSTem:PROFiling:RECORD
SYSTem:PROFiling:RECORD:CLEar
SYSTem:PROFiling:RECORD:IGNore
SYSTem:PROFiling:RECORD:SAVE
```

class RecordCls

Record commands group definition. 7 total commands, 2 Subgroups, 4 group commands

clear() → None

```
# SCPI: SYSTem:PROFiling:RECORD:CLEAr
driver.system.profiling.record.clear()
```

No command help available

clear_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:PROFiling:RECORD:CLEAr
driver.system.profiling.record.clear_with_opc()
```

No command help available

Same as clear, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get(index: List[str]) → List[str]

```
# SCPI: SYSTem:PROFiling:RECORD
value: List[str] = driver.system.profiling.record.get(index = ['abc1', 'abc2',
↪ 'abc3'])
```

No command help available

param index

No help available

return

index: No help available

get_ignore() → float

```
# SCPI: SYSTem:PROFiling:RECORD:IGNore
value: float = driver.system.profiling.record.get_ignore()
```

No command help available

return

count: No help available

save(filename: str) → None

```
# SCPI: SYSTem:PROFiling:RECORD:SAVE
driver.system.profiling.record.save(filename = 'abc')
```

No command help available

param filename

No help available

set_ignore(count: float) → None

```
# SCPI: SYSTem:PROFiling:RECORD:IGNore
driver.system.profiling.record.set_ignore(count = 1.0)
```

No command help available

param count
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.profiling.record.clone()
```

Subgroups

6.17.21.4.1 Count

SCPI Commands :

```
SYSTem:PROFiling:RECORD:COUNT:MAX
SYSTem:PROFiling:RECORD:COUNT
```

class CountCls

Count commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_max() → float

```
# SCPI: SYSTem:PROFiling:RECORD:COUNT:MAX
value: float = driver.system.profiling.record.count.get_max()
```

No command help available

return
count: No help available

get_value() → float

```
# SCPI: SYSTem:PROFiling:RECORD:COUNT
value: float = driver.system.profiling.record.count.get_value()
```

No command help available

return
count: No help available

set_max(count: float) → None

```
# SCPI: SYSTem:PROFiling:RECORD:COUNT:MAX
driver.system.profiling.record.count.set_max(count = 1.0)
```

No command help available

param count
No help available

6.17.21.4.2 Wrap

SCPI Command :

SYSTem:PROFiling:RECORD:WRAP:STATe

class WrapCls

Wrap commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:PROFiling:RECORD:WRAP:STATe
value: bool = driver.system.profiling.record.wrap.get_state()
```

No command help available

return
state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:PROFiling:RECORD:WRAP:STATe
driver.system.profiling.record.wrap.set_state(state = False)
```

No command help available

param state
No help available

6.17.21.5 Tick

SCPI Command :

SYSTem:PROFiling:TICK

class TickCls

Tick commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_value() → str

```
# SCPI: SYSTem:PROFiling:TICK
value: str = driver.system.profiling.tick.get_value()
```

No command help available

return
answer: No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.profiling.tick.clone()
```

Subgroups

6.17.21.5.1 Enable

SCPI Command :

```
SYSTem:PROFiling:TICK:ENABle
```

class EnableCls

Enable commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:PROFiling:TICK:ENABle
driver.system.profiling.tick.enable.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:PROFiling:TICK:ENABle
driver.system.profiling.tick.enable.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.21.6 Tpoint

SCPI Command :

```
SYSTem:PROFiling:TPOint:REStart
```

class TpointCls

Tpoint commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_restart() → List[str]

```
# SCPI: SYSTem:PROFiling:TPOint:REStart
value: List[str] = driver.system.profiling.tpoint.get_restart()
```

No command help available

```
    return
        module_and_tp: No help available
set_restart(module_and_tp: List[str]) → None
```

```
# SCPI: SYSTem:PROFiling:TPOint:REStart
driver.system.profiling.tpoint.set_restart(module_and_tp = ['abc1', 'abc2',
↪ 'abc3'])
```

No command help available

```
param module_and_tp
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.profiling.tpoint.clone()
```

Subgroups

6.17.21.6.1 Catalog

SCPI Command :

```
SYSTem:PROFiling:TPOint:CATalog
```

class CatalogCls

Catalog commands group definition. 1 total commands, 0 Subgroups, 1 group commands

```
get(name: str) → List[str]
```

```
# SCPI: SYSTem:PROFiling:TPOint:CATalog
value: List[str] = driver.system.profiling.tpoint.catalog.get(name = 'abc')
```

No command help available

```
param name
    No help available
```

```
return
    value: No help available
```

6.17.22 Protect<Level>

RepCap Settings

```
# Range: Nr1 .. Nr16
rc = driver.system.protect.repcap_level_get()
driver.system.protect.repcap_level_set(repcap.Level.Nr1)
```

class ProtectCls

Protect commands group definition. 1 total commands, 1 Subgroups, 0 group commands Repeated Capability: Level, default value after init: Level.Nr1

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.protect.clone()
```

Subgroups**6.17.22.1 State****SCPI Command :**

```
SYSTem:PROTect<CH>:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(level=Level.Default) → bool

```
# SCPI: SYSTem:PROTect<CH>:[STATe]
value: bool = driver.system.protect.state.get(level = repcap.Level.Default)
```

Activates and deactivates the specified protection level.

param level

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Protect’)

return

state: 0| 1| OFF| ON

set(state: bool, key: int = None, level=Level.Default) → None

```
# SCPI: SYSTem:PROTect<CH>:[STATe]
driver.system.protect.state.set(state = False, key = 1, level = repcap.Level.
↪Default)
```

Activates and deactivates the specified protection level.

param state

0| 1| OFF| ON

param key

integer The respective functions are disabled when the protection level is activated. No password is required for activation of a level. A password must be entered to deactivate the protection level. The default password for the first level is 123456. This protection level is required to unlock internal adjustments for example.

param level

optional repeated capability selector. Default value: Nr1 (settable in the interface ‘Protect’)

6.17.23 Reboot

SCPI Command :

```
SYSTem:REBoot
```

class RebootCls

Reboot commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:REBoot
driver.system.reboot.set()
```

Reboots the instrument including the operating system.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:REBoot
driver.system.reboot.set_with_opc()
```

Reboots the instrument including the operating system.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.24 Restart

SCPI Command :

```
SYSTem:REStArt
```

class RestartCls

Restart commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:REStArt
driver.system.restart.set()
```

Restarts the instrument without restarting the operating system.

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:REStArt
driver.system.restart.set_with_opc()
```

Restarts the instrument without restarting the operating system.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.25 Script

SCPI Commands :

```
SYSTem:SCRPt:ARG
SYSTem:SCRPt:CMD
SYSTem:SCRPt:DATA
SYSTem:SCRPt:RUN
```

class ScriptCls

Script commands group definition. 5 total commands, 1 Subgroups, 4 group commands

get_arg() → str

```
# SCPI: SYSTem:SCRPt:ARG
value: str = driver.system.scrpt.get_arg()
```

No command help available

return

arguments: No help available

get_cmd() → str

```
# SCPI: SYSTem:SCRPt:CMD
value: str = driver.system.scrpt.get_cmd()
```

No command help available

return

cmd_file: No help available

get_data() → str

```
# SCPI: SYSTem:SCRPt:DATA
value: str = driver.system.scrpt.get_data()
```

No command help available

return

data_file: No help available

run() → None

```
# SCPI: SYSTem:SCRPt:RUN
driver.system.scrpt.run()
```

No command help available

run_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SCRPt:RUN
driver.system.scrpt.run_with_opc()
```

No command help available

Same as run, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

set_arg(arguments: str) → None

```
# SCPI: SYSTem:SCRPt:ARG
driver.system.scrpt.set_arg(arguments = 'abc')
```

No command help available

param arguments

No help available

set_cmd(cmd_file: str) → None

```
# SCPI: SYSTem:SCRPt:CMD
driver.system.scrpt.set_cmd(cmd_file = 'abc')
```

No command help available

param cmd_file

No help available

set_data(data_file: str) → None

```
# SCPI: SYSTem:SCRPt:DATA
driver.system.scrpt.set_data(data_file = 'abc')
```

No command help available

param data_file

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.scrpt.clone()
```

Subgroups

6.17.25.1 Discard

SCPI Command :

```
SYSTem:SCRPt:DISCard
```

class DiscardCls

Discard commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:SCRpt:DISCard
driver.system.scrpt.discard.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SCRpt:DISCard
driver.system.scrpt.discard.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.26 Security

SCPI Command :

```
SYSTem:SECurity:[STATe]
```

class SecurityCls

Security commands group definition. 18 total commands, 6 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:SECurity:[STATe]
value: bool = driver.system.security.get_state()
```

No command help available

return

state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:SECurity:[STATe]
driver.system.security.set_state(state = False)
```

No command help available

param state

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.clone()
```

Subgroups

6.17.26.1 Mmem

class MmemCls

Mmem commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.mmem.clone()
```

Subgroups

6.17.26.1.1 Protect

class ProtectCls

Protect commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.mmem.protect.clone()
```

Subgroups

6.17.26.1.1.1 State

SCPI Command :

```
SYSTem:SECurity:MMEM:PROTect:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:MMEM:PROTect:[STATe]
value: bool = driver.system.security.mmem.protect.state.get()
```

No command help available


```

    return
        mmem_prot_state: No help available
set(sec_pass_word: str, mmem_prot_state: bool) → None

```

```

# SCPI: SYSTem:SECurity:MMEM:PROTect:[STATe]
driver.system.security.mmem.protect.state.set(sec_pass_word = 'abc', mmem_prot_
↪state = False)

```

No command help available

```

param sec_pass_word
    No help available

```

```

param mmem_prot_state
    No help available

```

6.17.26.2 Network

class NetworkCls

Network commands group definition. 12 total commands, 12 Subgroups, 0 group commands

Cloning the Group

```

# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.clone()

```

Subgroups

6.17.26.2.1 Avahi

class AvahiCls

Avahi commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```

# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.avahi.clone()

```

Subgroups

6.17.26.2.1.1 State

SCPI Command :

```

SYSTem:SECurity:NETWork:AVAHi:[STATe]

```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:AVAHi:[STAtE]
value: bool = driver.system.security.network.avahi.state.get()
```

No command help available

```
return
    avahi_state: No help available
```

set(sec_pass_word: str, avahi_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:AVAHi:[STAtE]
driver.system.security.network.avahi.state.set(sec_pass_word = 'abc', avahi_
↪state = False)
```

No command help available

```
param sec_pass_word
    No help available
```

```
param avahi_state
    No help available
```

6.17.26.2.2 Ftp**class FtpCls**

Ftp commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.ftp.clone()
```

Subgroups**6.17.26.2.2.1 State****SCPI Command :**

```
SYSTem:SECurity:NETWork:FTP:[STAtE]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:FTP:[STAtE]
value: bool = driver.system.security.network.ftp.state.get()
```

No command help available

```

return
    ftp_state: No help available

```

set(sec_pass_word: str, ftp_state: bool) → None

```

# SCPI: SYSTem:SECurity:NETWork:FTP:[STaTe]
driver.system.security.network.ftp.state.set(sec_pass_word = 'abc', ftp_state = False)

```

No command help available

```

param sec_pass_word
    No help available

```

```

param ftp_state
    No help available

```

6.17.26.2.3 Http

class HttpCls

Http commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```

# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.http.clone()

```

Subgroups

6.17.26.2.3.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:HTTP:[STaTe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```

# SCPI: SYSTem:SECurity:NETWork:HTTP:[STaTe]
value: bool = driver.system.security.network.http.state.get()

```

No command help available

```

return
    http_state: No help available

```

set(sec_pass_word: str, http_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:HTTP:[STAtE]
driver.system.security.network.http.state.set(sec_pass_word = 'abc', http_state_
↳ False)
```

No command help available

param sec_pass_word
No help available

param http_state
No help available

6.17.26.2.4 Raw

class RawCls

Raw commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.raw.clone()
```

Subgroups

6.17.26.2.4.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:RAW:[STAtE]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:RAW:[STAtE]
value: bool = driver.system.security.network.raw.state.get()
```

No command help available

return
raw_state: No help available

set(sec_pass_word: str, raw_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:RAW:[STAtE]
driver.system.security.network.raw.state.set(sec_pass_word = 'abc', raw_state =
↳ False)
```

No command help available

param sec_pass_word

No help available

param raw_state

No help available

6.17.26.2.5 RemSupport

SCPI Command :

```
SYSTem:SECurity:NETWork:REMSupport:[STATe]
```

class RemSupportCls

RemSupport commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:SECurity:NETWork:REMSupport:[STATe]
value: bool = driver.system.security.network.remSupport.get_state()
```

No command help available

return

net_rem_support: No help available

set_state(net_rem_support: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:REMSupport:[STATe]
driver.system.security.network.remSupport.set_state(net_rem_support = False)
```

No command help available

param net_rem_support

No help available

6.17.26.2.6 Rpc

class RpcCls

Rpc commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.rpc.clone()
```

Subgroups

6.17.26.2.6.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:RPC:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:RPC:[STATe]
value: bool = driver.system.security.network.rpc.state.get()
```

No command help available

```
return
    rpc_state: No help available
```

set(sec_pass_word: str, rpc_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:RPC:[STATe]
driver.system.security.network.rpc.state.set(sec_pass_word = 'abc', rpc_state =
↪False)
```

No command help available

```
param sec_pass_word
    No help available
```

```
param rpc_state
    No help available
```

6.17.26.2.7 Smb

class SmbCls

Smb commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.smb.clone()
```

Subgroups

6.17.26.2.7.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:SMB:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:SMB:[STATe]
value: bool = driver.system.security.network.smb.state.get()
```

No command help available

```
return
    smb_state: No help available
```

set(sec_pass_word: str, smb_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:SMB:[STATe]
driver.system.security.network.smb.state.set(sec_pass_word = 'abc', smb_state =
↪False)
```

No command help available

```
param sec_pass_word
    No help available
```

```
param smb_state
    No help available
```

6.17.26.2.8 Soe

class SoeCls

Soe commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.soe.clone()
```

Subgroups

6.17.26.2.8.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:SOE:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:SOE:[STATe]
value: bool = driver.system.security.network.soe.state.get()
```

No command help available

```
return
    soe_state: No help available
```

set(sec_pass_word: str, soe_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:SOE:[STATe]
driver.system.security.network.soe.state.set(sec_pass_word = 'abc', soe_state =
↪False)
```

No command help available

```
param sec_pass_word
    No help available
```

```
param soe_state
    No help available
```

6.17.26.2.9 Ssh

class SshCls

Ssh commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.ssh.clone()
```


Subgroups

6.17.26.2.9.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:SSH:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:SSH:[STATe]
value: bool = driver.system.security.network.ssh.state.get()
```

No command help available

```
return
    ssh_state: No help available
```

set(sec_pass_word: str, ssh_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:SSH:[STATe]
driver.system.security.network.ssh.state.set(sec_pass_word = 'abc', ssh_state =
↪False)
```

No command help available

```
param sec_pass_word
    No help available
param ssh_state
    No help available
```

6.17.26.2.10 State

SCPI Command :

```
SYSTem:SECurity:NETWork:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:[STATe]
value: bool = driver.system.security.network.state.get()
```

No command help available

```
return
    lan_stor_state: No help available
```

set(*sec_pass_word*: str, *lan_stor_state*: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:[STATe]
driver.system.security.network.state.set(sec_pass_word = 'abc', lan_stor_state_
↪= False)
```

No command help available

param sec_pass_word

No help available

param lan_stor_state

No help available

6.17.26.2.11 SwUpdate

class SwUpdateCls

SwUpdate commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.swUpdate.clone()
```

Subgroups

6.17.26.2.11.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:SWUPdate:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:SWUPdate:[STATe]
value: bool = driver.system.security.network.swUpdate.state.get()
```

No command help available

return

sw_update_state: No help available

set(*sec_pass_word*: str, *sw_update_state*: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:SWUPdate:[STATe]
driver.system.security.network.swUpdate.state.set(sec_pass_word = 'abc', sw_
↪update_state = False)
```

No command help available

param sec_pass_word

No help available

param sw_update_state

No help available

6.17.26.2.12 Vnc

class VncCls

Vnc commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.network.vnc.clone()
```

Subgroups

6.17.26.2.12.1 State

SCPI Command :

```
SYSTem:SECurity:NETWork:VNC:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:NETWork:VNC:[STATe]
value: bool = driver.system.security.network.vnc.state.get()
```

No command help available

return

vnc_state: No help available

set(sec_pass_word: str, vnc_state: bool) → None

```
# SCPI: SYSTem:SECurity:NETWork:VNC:[STATe]
driver.system.security.network.vnc.state.set(sec_pass_word = 'abc', vnc_state =
False)
```

No command help available

param sec_pass_word

No help available

param vnc_state

No help available

6.17.26.3 Sanitize

class SanitizeCls

Sanitize commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.sanitize.clone()
```

Subgroups

6.17.26.3.1 State

SCPI Command :

```
SYSTem:SECurity:SANitize:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:SANitize:[STATe]
value: bool = driver.system.security.sanitize.state.get()
```

Sanitizes the internal memory.

```
return
    mmem_prot_state: 0| 1| OFF| ON
```

set(sec_pass_word: str, mmem_prot_state: bool) → None

```
# SCPI: SYSTem:SECurity:SANitize:[STATe]
driver.system.security.sanitize.state.set(sec_pass_word = 'abc', mmem_prot_
→state = False)
```

Sanitizes the internal memory.

```
param sec_pass_word
    string

param mmem_prot_state
    0| 1| OFF| ON
```

6.17.26.4 SuPolicy

SCPI Command :

```
SYSTem:SECurity:SUPolicy
```

class SuPolicyCls

SuPolicy commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → UpdPolicyMode

```
# SCPI: SYSTem:SECurity:SUPolicy
value: enums.UpdPolicyMode = driver.system.security.suPolicy.get()
```

Configures the automatic signature verification for firmware installation.

```
return
    update_policy: STRict| CONFirm| IGNore
```

set(sec_pass_word: str, update_policy: UpdPolicyMode) → None

```
# SCPI: SYSTem:SECurity:SUPolicy
driver.system.security.suPolicy.set(sec_pass_word = 'abc', update_policy =
↳enums.UpdPolicyMode.CONFirm)
```

Configures the automatic signature verification for firmware installation.

```
param sec_pass_word
    string

param update_policy
    STRict| CONFirm| IGNore
```

6.17.26.5 UsbStorage

class UsbStorageCls

UsbStorage commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.usbStorage.clone()
```

Subgroups

6.17.26.5.1 State

SCPI Command :

```
SYSTem:SECurity:USBStorage:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:USBStorage:[STATe]
value: bool = driver.system.security.usbStorage.state.get()
```

No command help available

```
return
    usb_stor_state: No help available
```

set(sec_pass_word: str, usb_stor_state: bool) → None

```
# SCPI: SYSTem:SECurity:USBStorage:[STATe]
driver.system.security.usbStorage.state.set(sec_pass_word = 'abc', usb_stor_
↪state = False)
```

No command help available

```
param sec_pass_word
    No help available
```

```
param usb_stor_state
    No help available
```

6.17.26.6 VolMode**class VolModeCls**

VolMode commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.security.volMode.clone()
```

Subgroups**6.17.26.6.1 State****SCPI Command :**

```
SYSTem:SECurity:VOLMode:[STATe]
```

class StateCls

State commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get() → bool

```
# SCPI: SYSTem:SECurity:VOLMode:[STATe]
value: bool = driver.system.security.volMode.state.get()
```

Activates volatile mode, so that no user data can be written to the internal memory permanently. To enable volatile mode, reboot the instrument. Otherwise the change has no effect.

```
return
    mmem_prot_state: 0| 1| OFF| ON
```

set(*sec_pass_word: str, mmem_prot_state: bool*) → None

```
# SCPI: SYSTem:SECurity:VOLMode:[STaTe]
driver.system.security.volMode.state.set(sec_pass_word = 'abc', mmem_prot_state_
↪ False)
```

Activates volatile mode, so that no user data can be written to the internal memory permanently. To enable volatile mode, reboot the instrument. Otherwise the change has no effect.

```
param sec_pass_word
    string Current security password The default password is 123456.

param mmem_prot_state
    0| 1| OFF| ON
```

6.17.27 Shutdown

SCPI Command :

```
SYSTem:SHUTdown
```

class ShutdownCls

Shutdown commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:SHUTdown
driver.system.shutdown.set()
```

Shuts down the instrument.

set_with_opc(*opc_timeout_ms: int = -1*) → None

```
# SCPI: SYSTem:SHUTdown
driver.system.shutdown.set_with_opc()
```

Shuts down the instrument.

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

```
param opc_timeout_ms
    Maximum time to wait in milliseconds, valid only for this call.
```

6.17.28 SrData

SCPI Commands :

```
SYSTem:SRData:DElete  
SYSTem:SRData
```

class SrDataCls

SrData commands group definition. 2 total commands, 0 Subgroups, 2 group commands

delete() → None

```
# SCPI: SYSTem:SRData:DElete  
driver.system.srData.delete()
```

No command help available

delete_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SRData:DElete  
driver.system.srData.delete_with_opc()
```

No command help available

Same as delete, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

get_value() → bytes

```
# SCPI: SYSTem:SRData  
value: bytes = driver.system.srData.get_value()
```

Queris the SCPI recording data from the internal file. This feature enables you to transfer an instrument configuration to other test environments, as e.g. laboratory virtual instruments.

return

file_data: block data

6.17.29 Srexec

SCPI Command :

```
SYSTem:SREXec
```

class SrexecCls

Srexec commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:SREXec  
driver.system.srexec.set()
```


No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:SREXec
driver.system.srexec.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.30 Srtime

SCPI Command :

```
SYSTem:SRTIME:STATe
```

class SrtimeCls

Srtime commands group definition. 2 total commands, 1 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:SRTIME:STATe
value: bool = driver.system.srtime.get_state()
```

No command help available

return

state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:SRTIME:STATe
driver.system.srtime.set_state(state = False)
```

No command help available

param state

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.srtime.clone()
```

Subgroups

6.17.30.1 Synchronize

SCPI Command :

```
SYSTem:SRTIME:SYNChronize
```

class SynchronizeCls

Synchronize commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(time: str) → str

```
# SCPI: SYSTem:SRTIME:SYNChronize
value: str = driver.system.srtime.synchronize.get(time = 'abc')
```

No command help available

param time

No help available

return

time: No help available

6.17.31 Startup

SCPI Command :

```
SYSTem:STARtup:COMPLete
```

class StartupCls

Startup commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get_complete() → bool

```
# SCPI: SYSTem:STARtup:COMPLete
value: bool = driver.system.startup.get_complete()
```

Queries if the startup of the instrument is completed.

return

complete: 0| 1| OFF| ON

6.17.32 Time

SCPI Commands :

```
SYSTem:TIME
SYSTem:TIME:LOCal
SYSTem:TIME:PROTocol
SYSTem:TIME:UTC
```

class TimeCls

Time commands group definition. 12 total commands, 3 Subgroups, 4 group commands

class TimeStruct

Response structure. Fields:

- Hour: List[int]: integer Range: 0 to 23
- Minute: int: integer Range: 0 to 59
- Second: int: integer Range: 0 to 59

get() → TimeStruct

```
# SCPI: SYSTem:TIME
value: TimeStruct = driver.system.time.get()
```

Queries or sets the time for the instrument-internal clock. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg.System.Protect.State.set.

return

structure: for return value, see the help for TimeStruct structure arguments.

get_local() → str

```
# SCPI: SYSTem:TIME:LOCal
value: str = driver.system.time.get_local()
```

No command help available

return

pseudo_string: No help available

get_protocol() → TimeProtocol

```
# SCPI: SYSTem:TIME:PROToCol
value: enums.TimeProtocol = driver.system.time.get_protocol()
```

No command help available

return

time_protocol: No help available

get_utc() → str

```
# SCPI: SYSTem:TIME:UTC
value: str = driver.system.time.get_utc()
```

No command help available

return

pseudo_string: No help available

set(hour: List[int], minute: int, second: int) → None

```
# SCPI: SYSTem:TIME
driver.system.time.set(hour = [1, 2, 3], minute = 1, second = 1)
```

Queries or sets the time for the instrument-internal clock. This is a password-protected function. Unlock the protection level 1 to access it. See method RsAreg.System.Protect.State.set.

param hour
integer Range: 0 to 23

param minute
integer Range: 0 to 59

param second
integer Range: 0 to 59

set_local(*pseudo_string: str*) → None

```
# SCPI: SYSTem:TIME:LOCaL
driver.system.time.set_local(pseudo_string = 'abc')
```

No command help available

param pseudo_string
No help available

set_protocol(*time_protocol: TimeProtocol*) → None

```
# SCPI: SYSTem:TIME:PROTOcol
driver.system.time.set_protocol(time_protocol = enums.TimeProtocol._0)
```

No command help available

param time_protocol
No help available

set_utc(*pseudo_string: str*) → None

```
# SCPI: SYSTem:TIME:UTC
driver.system.time.set_utc(pseudo_string = 'abc')
```

No command help available

param pseudo_string
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.clone()
```

Subgroups

6.17.32.1 DaylightSavingTime

SCPI Command :

```
SYSTem:TIME:DSTime:MODE
```

class DaylightSavingTimeCls

DaylightSavingTime commands group definition. 3 total commands, 1 Subgroups, 1 group commands

get_mode() → str

```
# SCPI: SYSTem:TIME:DSTime:MODE
value: str = driver.system.time.daylightSavingTime.get_mode()
```

No command help available

```
return
pseudo_string: No help available
```

set_mode(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:DSTime:MODE
driver.system.time.daylightSavingTime.set_mode(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.daylightSavingTime.clone()
```

Subgroups

6.17.32.1.1 Rule

SCPI Commands :

```
SYSTem:TIME:DSTime:RULE:CATalog
SYSTem:TIME:DSTime:RULE
```

class RuleCls

Rule commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → str

```
# SCPI: SYSTem:TIME:DSTime:RULE:CATalog
value: str = driver.system.time.daylightSavingTime.rule.get_catalog()
```

No command help available

```
return
pseudo_string: No help available
```

get_value() → str

```
# SCPI: SYSTem:TIME:DSTime:RULE
value: str = driver.system.time.daylightSavingTime.rule.get_value()
```

No command help available

```
        return
        pseudo_string: No help available
set_value(pseudo_string: str) → None
```

```
# SCPI: SYSTem:TIME:DSTime:RULE
driver.system.time.daylightSavingTime.rule.set_value(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
    No help available
```

6.17.32.2 HrTimer

SCPI Command :

```
SYSTem:TIME:HRTimer:RELative
```

class HrTimerCls

HrTimer commands group definition. 3 total commands, 1 Subgroups, 1 group commands

```
set_relative(pseudo_string: str) → None
```

```
# SCPI: SYSTem:TIME:HRTimer:RELative
driver.system.time.hrTimer.set_relative(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.time.hrTimer.clone()
```

Subgroups

6.17.32.2.1 Absolute

SCPI Commands :

```
SYSTem:TIME:HRTimer:ABSolute:SET
SYSTem:TIME:HRTimer:ABSolute
```

class AbsoluteCls

Absolute commands group definition. 2 total commands, 0 Subgroups, 2 group commands

```
get_set() → str
```

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute:SET
value: str = driver.system.time.hrTimer.absolute.get_set()
```

No command help available

```
return
    pseudo_string: No help available
```

set_set(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute:SET
driver.system.time.hrTimer.absolute.set_set(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
    No help available
```

set_value(pseudo_string: str) → None

```
# SCPI: SYSTem:TIME:HRTimer:ABSolute
driver.system.time.hrTimer.absolute.set_value(pseudo_string = 'abc')
```

No command help available

```
param pseudo_string
    No help available
```

6.17.32.3 Zone

SCPI Commands :

```
SYSTem:TIME:ZONE:CATalog
SYSTem:TIME:ZONE
```

class ZoneCls

Zone commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: SYSTem:TIME:ZONE:CATalog
value: List[str] = driver.system.time.zone.get_catalog()
```

Querys the list of available timezones.

```
return
    catalog: No help available
```

get_value() → str

```
# SCPI: SYSTem:TIME:ZONE
value: str = driver.system.time.zone.get_value()
```

Sets the timezone. You can query the list of the available timezones with method RsAreg.System.Time.Zone.catalog.

```

    return
        time_zone: string

set_value(time_zone: str) → None

```

```

# SCPI: SYSTem:TIME:ZONE
driver.system.time.zone.set_value(time_zone = 'abc')

```

Sets the timezone. You can query the list of the available timezones with method `RsAreg.System.Time.Zone.catalog`.

```

param time_zone
    string

```

6.17.33 Ulock

SCPI Command :

```
SYSTem:ULOCK
```

class UlockCls

Ulock commands group definition. 1 total commands, 0 Subgroups, 1 group commands

`get()` → `DispKeybLockMode`

```

# SCPI: SYSTem:ULOCK
value: enums.DispKeybLockMode = driver.system.ulock.get()

```

Locks or unlocks the user interface of the instrument.

```

return
    mode: ENABLEd| DONLy| DISAbled| TOFF| VNConly ENABLEd Unlocks the display,
    the touchscreen and all controls for the manual operation. DONLy Locks the touch-
    screen and controls for the manual operation of the instrument. The display shows the
    current settings. VNConly Locks the touchscreen and controls for the manual opera-
    tion, and enables remote operation over VNC. The display shows the current settings.
    TOFF Locks the touchscreen for the manual operation of the instrument. The dis-
    play shows the current settings. DISAbled Locks the display, the touchscreen and all
    controls for the manual operation.

```

`set(sec_pass_word: str, mode: DispKeybLockMode)` → None

```

# SCPI: SYSTem:ULOCK
driver.system.ulock.set(sec_pass_word = 'abc', mode = enums.DispKeybLockMode.
↳DISAbled)

```

Locks or unlocks the user interface of the instrument.

```

param sec_pass_word
    No help available

```

```

param mode
    ENABLEd| DONLy| DISAbled| TOFF| VNConly ENABLEd Unlocks the display, the
    touchscreen and all controls for the manual operation. DONLy Locks the touchscreen
    and controls for the manual operation of the instrument. The display shows the current
    settings. VNConly Locks the touchscreen and controls for the manual operation, and

```


enables remote operation over VNC. The display shows the current settings. TOFF Locks the touchscreen for the manual operation of the instrument. The display shows the current settings. DISabled Locks the display, the touchscreen and all controls for the manual operation.

6.17.34 Undo

SCPI Command :

```
SYSTem:UNDO:STATe
```

class UndoCls

Undo commands group definition. 5 total commands, 3 Subgroups, 1 group commands

get_state() → bool

```
# SCPI: SYSTem:UNDO:STATe
value: bool = driver.system.undo.get_state()
```

No command help available

return
state: No help available

set_state(state: bool) → None

```
# SCPI: SYSTem:UNDO:STATe
driver.system.undo.set_state(state = False)
```

No command help available

param state
No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.system.undo.clone()
```

Subgroups

6.17.34.1 Hclear

SCPI Command :

```
SYSTem:UNDO:HCLear
```

class HclearCls

Hclear commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set() → None

```
# SCPI: SYSTem:UNDO:HCLear
driver.system.undo.hclear.set()
```

No command help available

set_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: SYSTem:UNDO:HCLear
driver.system.undo.hclear.set_with_opc()
```

No command help available

Same as set, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

6.17.34.2 Hid

SCPI Command :

```
SYSTem:UNDO:HID:SElect
```

class HidCls

Hid commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set_select(select: int) → None

```
# SCPI: SYSTem:UNDO:HID:SElect
driver.system.undo.hid.set_select(select = 1)
```

No command help available

param select

No help available

6.17.34.3 Hlable

SCPI Commands :

```
SYSTem:UNDO:HLABLE:CATalog
SYSTem:UNDO:HLABLE:SElect
```

class HlableCls

Hlable commands group definition. 2 total commands, 0 Subgroups, 2 group commands

get_catalog() → List[str]

```
# SCPI: SYSTem:UNDO:HLABLE:CATalog
value: List[str] = driver.system.undo.hlable.get_catalog()
```

No command help available

return

catalog: No help available

set_select(*label: str*) → None

```
# SCPI: SYSTem:UNDO:HLABle:SElect
driver.system.undo.hlable.set_select(label = 'abc')
```

No command help available

param label

No help available

6.18 Test

SCPI Commands :

```
TEST:HS
TEST:LEVel
TEST:NRPTTrigger
TEST:PRESet
```

class TestCls

Test commands group definition. 19 total commands, 7 Subgroups, 4 group commands

get_hs() → str

```
# SCPI: TEST:HS
value: str = driver.test.get_hs()
```

No command help available

return

arg_test_int_face: No help available

get_level() → SelftLev

```
# SCPI: TEST:LEVel
value: enums.SelftLev = driver.test.get_level()
```

No command help available

return

level: No help available

preset() → None

```
# SCPI: TEST:PRESet
driver.test.preset()
```

No command help available

preset_with_opc(opc_timeout_ms: int = -1) → None

```
# SCPI: TEST:PRESet
driver.test.preset_with_opc()
```

No command help available

Same as preset, but waits for the operation to complete before continuing further. Use the RsAreg.utilities.opc_timeout_set() to set the timeout value.

param opc_timeout_ms

Maximum time to wait in milliseconds, valid only for this call.

set_hs(areg_test_int_face: str) → None

```
# SCPI: TEST:HS
driver.test.set_hs(areg_test_int_face = 'abc')
```

No command help available

param areg_test_int_face

No help available

set_level(level: SelftLev) → None

```
# SCPI: TEST:LEVel
driver.test.set_level(level = enums.SelftLev.CUSTOMer)
```

No command help available

param level

No help available

set_nrp_trigger(nrp_trigger: bool) → None

```
# SCPI: TEST:NRPTriTrigger
driver.test.set_nrp_trigger(nrp_trigger = False)
```

No command help available

param nrp_trigger

No help available

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.clone()
```

Subgroups

6.18.1 Device

class DeviceCls

Device commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.device.clone()
```

Subgroups

6.18.1.1 Internal

SCPI Command :

```
TEST:DEvice:INTernal
```

class InternalCls

Internal commands group definition. 1 total commands, 0 Subgroups, 1 group commands

get(argument: str) → Test

```
# SCPI: TEST:DEvice:INTernal
value: enums.Test = driver.test.device.internal.get(argument = 'abc')
```

No command help available

param argument
No help available

return
result: No help available

6.18.2 Pixel

SCPI Commands :

```
TEST:PIXel:COLor
TEST:PIXel:GRADient
TEST:PIXel:POINTsize
TEST:PIXel:RGBA
TEST:PIXel:TEXT
TEST:PIXel:WINDow
```

class PixelCls

Pixel commands group definition. 6 total commands, 0 Subgroups, 6 group commands

get_gradient() → bool

```
# SCPI: TEST:PIXel:GRADient
value: bool = driver.test.pixel.get_gradient()
```

No command help available

```
return
    pix_test_grad_stat: No help available
```

get_point_size() → int

```
# SCPI: TEST:PIXel:POINTsize
value: int = driver.test.pixel.get_point_size()
```

No command help available

```
return
    pix_test_grad_stat: No help available
```

get_rgba() → List[int]

```
# SCPI: TEST:PIXel:RGBA
value: List[int] = driver.test.pixel.get_rgba()
```

No command help available

```
return
    pixel_test_rgba: No help available
```

get_text() → bool

```
# SCPI: TEST:PIXel:TEXT
value: bool = driver.test.pixel.get_text()
```

No command help available

```
return
    pix_test_grad_stat: No help available
```

set_color()(*pix_test_color: PixelTestPredefined*) → None

```
# SCPI: TEST:PIXel:COLor
driver.test.pixel.set_color(pix_test_color = enums.PixelTestPredefined.AUTO)
```

No command help available

```
param pix_test_color
    No help available
```

set_gradient()(*pix_test_grad_stat: bool*) → None

```
# SCPI: TEST:PIXel:GRADient
driver.test.pixel.set_gradient(pix_test_grad_stat = False)
```

No command help available

```
param pix_test_grad_stat
    No help available
```

set_point_size(*pix_test_grad_stat: int*) → None

```
# SCPI: TEST:PIXel:POINTsize
driver.test.pixel.set_point_size(pix_test_grad_stat = 1)
```

No command help available

param pix_test_grad_stat
No help available

set_rgba(*pixel_test_rgba: List[int]*) → None

```
# SCPI: TEST:PIXel:RGBA
driver.test.pixel.set_rgba(pixel_test_rgba = [1, 2, 3])
```

No command help available

param pixel_test_rgba
No help available

set_text(*pix_test_grad_stat: bool*) → None

```
# SCPI: TEST:PIXel:TEXT
driver.test.pixel.set_text(pix_test_grad_stat = False)
```

No command help available

param pix_test_grad_stat
No help available

set_window(*pix_test_window: bool*) → None

```
# SCPI: TEST:PIXel:WINDOW
driver.test.pixel.set_window(pix_test_window = False)
```

No command help available

param pix_test_window
No help available

6.18.3 Remote

class RemoteCls

Remote commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.remote.clone()
```

Subgroups

6.18.3.1 Lockout

SCPI Command :

```
TEST<HW>:REMOte:LOCKout:[STATe]
```

class LockoutCls

Lockout commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set_state(state: bool) → None

```
# SCPI: TEST<HW>:REMOte:LOCKout:[STATe]
driver.test.remote.lockout.set_state(state = False)
```

No command help available

param state

No help available

6.18.4 Res

SCPI Commands :

```
TEST:RES:COLor
TEST:RES:TEXT
TEST:RES:WIND
```

class ResCls

Res commands group definition. 3 total commands, 0 Subgroups, 3 group commands

get_color() → Colour

```
# SCPI: TEST:RES:COLor
value: enums.Colour = driver.test.res.get_color()
```

No command help available

return

color: No help available

get_text() → str

```
# SCPI: TEST:RES:TEXT
value: str = driver.test.res.get_text()
```

No command help available

return

text: No help available

get_wind() → bool


```
# SCPI: TEST:RES:WIND
value: bool = driver.test.res.get_wind()
```

No command help available

```
return
    state: No help available
```

set_color(color: Colour) → None

```
# SCPI: TEST:RES:COLor
driver.test.res.set_color(color = enums.Colour.GREEN)
```

No command help available

```
param color
    No help available
```

set_text(text: str) → None

```
# SCPI: TEST:RES:TEXT
driver.test.res.set_text(text = 'abc')
```

No command help available

```
param text
    No help available
```

set_wind(state: bool) → None

```
# SCPI: TEST:RES:WIND
driver.test.res.set_wind(state = False)
```

No command help available

```
param state
    No help available
```

6.18.5 Serror

SCPI Command :

```
TEST:SERRor:UNSet
```

class SerrorCls

Error commands group definition. 2 total commands, 1 Subgroups, 1 group commands

set_unset(path: int) → None

```
# SCPI: TEST:SERRor:UNSet
driver.test.serror.set_unset(path = 1)
```

No command help available

```
param path
    No help available
```

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.serror.clone()
```

Subgroups

6.18.5.1 Set

SCPI Command :

```
TEST:SERRor:SET
```

class SetCls

Set commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set(err_code: int, path: int) → None

```
# SCPI: TEST:SERRor:SET
driver.test.serror.set.set(err_code = 1, path = 1)
```

No command help available

param err_code
No help available

param path
No help available

6.18.6 Sw

class SwCls

Sw commands group definition. 1 total commands, 1 Subgroups, 0 group commands

Cloning the Group

```
# Create a clone of the original group, that exists independently
group2 = driver.test.sw.clone()
```

Subgroups

6.18.6.1 Scmd

SCPI Command :

```
TEST<HW>:SW:SCMD
```

class ScmdCls

Scmd commands group definition. 1 total commands, 0 Subgroups, 1 group commands

class ScmdStruct

Response structure. Fields:

- Scmd: str: No parameter help available
- What_Is_This: str: No parameter help available

get() → ScmdStruct

```
# SCPI: TEST<HW>:SW:SCMD
value: ScmdStruct = driver.test.sw.scmd.get()
```

No command help available

return

structure: for return value, see the help for ScmdStruct structure arguments.

set(scmd: str, what_is_this: str) → None

```
# SCPI: TEST<HW>:SW:SCMD
driver.test.sw.scmd.set(scmd = 'abc', what_is_this = 'abc')
```

No command help available

param scmd

No help available

param what_is_this

No help available

6.18.7 Write

SCPI Command :

```
TEST:WRITE:RESult
```

class WriteCls

Write commands group definition. 1 total commands, 0 Subgroups, 1 group commands

set_result(result: SelfLevWrite) → None

```
# SCPI: TEST:WRITE:RESult
driver.test.write.set_result(result = enums.SelfLevWrite.CUSTOMer)
```

No command help available

param result

No help available

RSAREG UTILITIES

class Utilities

Common utility class. Utility functions common for all types of drivers.

Access snippet: `utils = RsAreg.utilities`

property logger: *ScpiLogger*

Scpi Logger interface, see [here](#)

Access snippet: `logger = RsAreg.utilities.logger`

property driver_version: `str`

Returns the instrument driver version.

property idn_string: `str`

Returns instrument's identification string - the response on the SCPI command `*IDN?`

property manufacturer: `str`

Returns manufacturer of the instrument.

property full_instrument_model_name: `str`

Returns the current instrument's full name e.g. 'FSW26'.

property instrument_model_name: `str`

Returns the current instrument's family name e.g. 'FSW'.

property supported_models: `List[str]`

Returns a list of the instrument models supported by this instrument driver.

property instrument_firmware_version: `str`

Returns instrument's firmware version.

property instrument_serial_number: `str`

Returns instrument's serial_number.

query_opc(*timeout: int = 0*) → `int`

SCPI command: `*OPC?` Queries the instrument's OPC bit and hence it waits until the instrument reports operation complete. If you define `timeout > 0`, the VISA timeout is set to that value just for this method call.

property instrument_status_checking: `bool`

Sets / returns Instrument Status Checking. When True (default is True), all the driver methods and properties are sending "SYSTem:ERRor?" at the end to immediately react on error that might have occurred. We recommend to keep the state checking ON all the time. Switch it OFF only in rare cases when you require maximum speed. The default state after initializing the session is ON.

property encoding: str

Returns string<=>bytes encoding of the session.

property opc_query_after_write: bool

Sets / returns Instrument *OPC? query sending after each command write. When True, (default is False) the driver sends *OPC? every time a write command is performed. Use this if you want to make sure your sequence is performed command-after-command.

property bin_float_numbers_format: BinFloatFormat

Sets / returns format of float numbers when transferred as binary data.

property bin_int_numbers_format: BinIntFormat

Sets / returns format of integer numbers when transferred as binary data.

clear_status() → None

Clears instrument's status system, the session's I/O buffers and the instrument's error queue.

query_all_errors() → List[str]

Queries and clears all the errors from the instrument's error queue. The method returns list of strings as error messages. If no error is detected, the return value is None. The process is: querying 'SYSTEM:ERRor?' in a loop until the error queue is empty. If you want to include the error codes, call the query_all_errors_with_codes()

query_all_errors_with_codes() → List[Tuple[int, str]]

Queries and clears all the errors from the instrument's error queue. The method returns list of tuples (code: int, message: str). If no error is detected, the return value is None. The process is: querying 'SYSTEM:ERRor?' in a loop until the error queue is empty.

property instrument_options: List[str]

Returns all the instrument options. The options are sorted in the ascending order starting with K-options and continuing with B-options.

reset() → None

SCPI command: *RST Sends *RST command + calls the clear_status().

default_instrument_setup() → None

Custom steps performed at the init and at the reset().

self_test(timeout: int = None) → Tuple[int, str]

SCPI command: *TST? Performs instrument's self-test. Returns tuple (code:int, message: str). Code 0 means the self-test passed. You can define the custom timeout in milliseconds. If you do not define it, the default selftest timeout is used (usually 60 secs).

is_connection_active() → bool

Returns true, if the VISA connection is active and the communication with the instrument still works.

reconnect(force_close: bool = False) → bool

If the connection is not active, the method tries to reconnect to the device. If the connection is active, and force_close is False, the method does nothing. If the connection is active, and force_close is True, the method closes, and opens the session again. Returns True, if the reconnection has been performed.

property resource_name: int

Returns the resource name used in the constructor

property opc_timeout: int

Sets / returns timeout in milliseconds for all the operations that use OPC synchronization.

property visa_timeout: int

Sets / returns visa IO timeout in milliseconds.

property data_chunk_size: int

Sets / returns the maximum size of one block transferred during write/read operations

property visa_manufacturer: int

Returns the manufacturer of the current VISA session.

process_all_commands() → None

SCPI command: **WAI* Stops further commands processing until all commands sent before **WAI* have been executed.

write_str(cmd: str) → None

Writes the command to the instrument.

write(cmd: str) → None

This method is an alias to the write_str(). Writes the command to the instrument as string.

write_int(cmd: str, param: int) → None

Writes the command to the instrument followed by the integer parameter: e.g.: cmd = 'SELECT:INPUT' param = '2', result command = 'SELECT:INPUT 2'

write_int_with_opc(cmd: str, param: int, timeout: int = None) → None

Writes the command with OPC to the instrument followed by the integer parameter: e.g.: cmd = 'SELECT:INPUT' param = '2', result command = 'SELECT:INPUT 2' If you do not provide timeout, the method uses current opc_timeout.

write_float(cmd: str, param: float) → None

Writes the command to the instrument followed by the boolean parameter: e.g.: cmd = 'CENTER:FREQ' param = '10E6', result command = 'CENTER:FREQ 10E6'

write_float_with_opc(cmd: str, param: float, timeout: int = None) → None

Writes the command with OPC to the instrument followed by the boolean parameter: e.g.: cmd = 'CENTER:FREQ' param = '10E6', result command = 'CENTER:FREQ 10E6' If you do not provide timeout, the method uses current opc_timeout.

write_bool(cmd: str, param: bool) → None

Writes the command to the instrument followed by the boolean parameter: e.g.: cmd = 'OUTPUT' param = 'True', result command = 'OUTPUT ON'

write_bool_with_opc(cmd: str, param: bool, timeout: int = None) → None

Writes the command with OPC to the instrument followed by the boolean parameter: e.g.: cmd = 'OUTPUT' param = 'True', result command = 'OUTPUT ON' If you do not provide timeout, the method uses current opc_timeout.

query_str(query: str) → str

Sends the query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit.

query(query: str) → str

This method is an alias to the query_str(). Sends the query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit.

query_bool(query: str) → bool

Sends the query to the instrument and returns the response as boolean.

query_int(*query: str*) → int

Sends the query to the instrument and returns the response as integer.

query_float(*query: str*) → float

Sends the query to the instrument and returns the response as float.

write_str_with_opc(*cmd: str, timeout: int = None*) → None

Writes the opc-synced command to the instrument. If you do not provide timeout, the method uses current `opc_timeout`.

write_with_opc(*cmd: str, timeout: int = None*) → None

This method is an alias to the `write_str_with_opc()`. Writes the opc-synced command to the instrument. If you do not provide timeout, the method uses current `opc_timeout`.

query_str_with_opc(*query: str, timeout: int = None*) → str

Sends the opc-synced query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit. If you do not provide timeout, the method uses current `opc_timeout`.

query_with_opc(*query: str, timeout: int = None*) → str

This method is an alias to the `query_str_with_opc()`. Sends the opc-synced query to the instrument and returns the response as string. The response is trimmed of any trailing LF characters and has no length limit. If you do not provide timeout, the method uses current `opc_timeout`.

query_bool_with_opc(*query: str, timeout: int = None*) → bool

Sends the opc-synced query to the instrument and returns the response as boolean. If you do not provide timeout, the method uses current `opc_timeout`.

query_int_with_opc(*query: str, timeout: int = None*) → int

Sends the opc-synced query to the instrument and returns the response as integer. If you do not provide timeout, the method uses current `opc_timeout`.

query_float_with_opc(*query: str, timeout: int = None*) → float

Sends the opc-synced query to the instrument and returns the response as float. If you do not provide timeout, the method uses current `opc_timeout`.

write_bin_block(*cmd: str, payload: bytes*) → None

Writes all the payload as binary data block to the instrument. The binary data header is added at the beginning of the transmission automatically, do not include it in the payload!!!

query_bin_block(*query: str*) → bytes

Queries binary data block to bytes. Throws an exception if the returned data was not a binary data. Returns `data:bytes`

query_bin_block_with_opc(*query: str, timeout: int = None*) → bytes

Sends a OPC-synced query and returns binary data block to bytes. If you do not provide timeout, the method uses current `opc_timeout`.

query_bin_or_ascii_float_list(*query: str*) → List[float]

Queries a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property `BinFloatFormat`, usually float 32-bit (FORM REAL,32).

query_bin_or_ascii_float_list_with_opc(*query: str, timeout: int = None*) → List[float]

Sends a OPC-synced query and reads a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property `BinFloatFormat`, usually float 32-bit (FORM REAL,32). If you do not provide timeout, the method uses current `opc_timeout`.

query_bin_or_ascii_int_list(*query: str*) → List[int]

Queries a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property BinFloatFormat, usually float 32-bit (FORM REAL,32).

query_bin_or_ascii_int_list_with_opc(*query: str, timeout: int = None*) → List[int]

Sends a OPC-synced query and reads a list of floating-point numbers that can be returned in ASCII format or in binary format. - For ASCII format, the list numbers are decoded as comma-separated values. - For Binary Format, the numbers are decoded based on the property BinFloatFormat, usually float 32-bit (FORM REAL,32). If you do not provide timeout, the method uses current `opc_timeout`.

query_bin_block_to_file(*query: str, file_path: str, append: bool = False*) → None

Queries binary data block to the provided file. If `append` is `False`, any existing file content is discarded. If `append` is `True`, the new content is added to the end of the existing file, or if the file does not exist, it is created. Throws an exception if the returned data was not a binary data. Example for transferring a file from Instrument -> PC: `query = f"MMEM:DATA? '{INSTR_FILE_PATH}'"`. Alternatively, use the dedicated methods for this purpose:

- `send_file_from_pc_to_instrument()`
- `read_file_from_instrument_to_pc()`

query_bin_block_to_file_with_opc(*query: str, file_path: str, append: bool = False, timeout: int = None*) → None

Sends a OPC-synced query and writes the returned data to the provided file. If `append` is `False`, any existing file content is discarded. If `append` is `True`, the new content is added to the end of the existing file, or if the file does not exist, it is created. Throws an exception if the returned data was not a binary data.

write_bin_block_from_file(*cmd: str, file_path: str*) → None

Writes data from the file as binary data block to the instrument using the provided command. Example for transferring a file from PC -> Instrument: `cmd = f"MMEM:DATA '{INSTR_FILE_PATH}',"`. Alternatively, use the dedicated methods for this purpose:

- `send_file_from_pc_to_instrument()`
- `read_file_from_instrument_to_pc()`

send_file_from_pc_to_instrument(*source_pc_file: str, target_instr_file: str*) → None

SCPI Command: `MMEM:DATA`

Sends file from PC to the instrument

read_file_from_instrument_to_pc(*source_instr_file: str, target_pc_file: str, append_to_pc_file: bool = False*) → None

SCPI Command: `MMEM:DATA?`

Reads file from instrument to the PC.

Set the `append_to_pc_file` to `True` if you want to append the read content to the end of the existing PC file

get_last_sent_cmd() → str

Returns the last commands sent to the instrument. Only works in simulation mode

go_to_local() → None

Puts the instrument into local state.

go_to_remote() → None

Puts the instrument into remote state.

get_lock() → RLock

Returns the thread lock for the current session.

By default:

- If you create standard new RsAreg instance with new VISA session, the session gets a new thread lock. You can assign it to other RsAreg sessions in order to share one physical instrument with a multi-thread access.
- If you create new RsAreg from an existing session, the thread lock is shared automatically making both instances multi-thread safe.

You can always assign new thread lock by calling `driver.utilities.assign_lock()`

assign_lock(lock: RLock) → None

Assigns the provided thread lock.

clear_lock()

Clears the existing thread lock, making the current session thread-independent from others that might share the current thread lock.

sync_from(source: Utilities) → None

Synchronises these Utils with the source.

RSAREG LOGGER

Check the usage in the Getting Started chapter [here](#).

class ScpiLogger

Base class for SCPI logging

mode

Sets the logging ON or OFF. Additionally, you can set the logging ON only for errors. Possible values:

- `LoggingMode.Off` - logging is switched OFF
- `LoggingMode.On` - logging is switched ON
- `LoggingMode.Errors` - logging is switched ON, but only for error entries
- `LoggingMode.Default` - sets the logging to default - the value you have set with `logger.default_mode`

default_mode

Sets / returns the default logging mode. You can recall the default mode by calling the `logger.mode = LoggingMode.Default`.

Data Type

`LoggingMode`

device_name: str

Use this property to change the resource name in the log from the default Resource Name (e.g. `TCPIP::192.168.2.101::INSTR`) to another name e.g. `'MySigGen1'`.

set_logging_target(target, console_log: bool = None, udp_log: bool = None) → None

Sets logging target - the target must implement `write()` and `flush()`. You can optionally set the console and UDP logging ON or OFF. This method switches the logging target global OFF.

get_logging_target()

Based on the `global_mode`, it returns the logging target: either the local or the global one.

set_logging_target_global(console_log: bool = None, udp_log: bool = None) → None

Sets logging target to global. The global target must be defined. You can optionally set the console and UDP logging ON or OFF.

log_to_console

Returns logging to console status.

log_to_udp

Returns logging to UDP status.

log_to_console_and_udp

Returns true, if both logging to UDP and console in are True.

info_raw(log_entry: str, add_new_line: bool = True) → None

Method for logging the raw string without any formatting.

info(start_time: datetime, end_time: datetime, log_string_info: str, log_string: str) → None

Method for logging one info entry. For binary log_string, use the info_bin()

error(start_time: datetime, end_time: datetime, log_string_info: str, log_string: str) → None

Method for logging one error entry.

set_relative_timestamp(timestamp: datetime) → None

If set, the further timestamps will be relative to the entered time.

set_relative_timestamp_now() → None

Sets the relative timestamp to the current time.

get_relative_timestamp() → datetime

Based on the global_mode, it returns the relative timestamp: either the local or the global one.

clear_relative_timestamp() → None

Clears the reference time, and the further logging continues with absolute times.

flush() → None

Flush all the entries.

log_status_check_ok

Sets / returns the current status of status checking OK. If True (default), the log contains logging of the status checking 'Status check: OK'. If False, the 'Status check: OK' is skipped - the log is more compact. Errors will still be logged.

clear_cached_entries() → None

Clears potential cached log entries. Cached log entries are generated when the Logging is ON, but no target has been defined yet.

set_format_string(value: str, line_divider: str = '\n') → None

Sets new format string and line divider. If you just want to set the line divider, set the format string value=None. The original format string is: PAD_LEFT12(%START_TIME%) PAD_LEFT25(%DEVICE_NAME%) PAD_LEFT12(%DURATION%) %LOG_STRING_INFO% %LOG_STRING%

restore_format_string() → None

Restores the original format string and the line divider to LF

abbreviated_max_len_ascii: int

Defines the maximum length of one ASCII log entry. Default value is 200 characters.

abbreviated_max_len_bin: int

Defines the maximum length of one Binary log entry. Default value is 2048 bytes.

abbreviated_max_len_list: int

Defines the maximum length of one list entry. Default value is 100 elements.

bin_line_block_size: int

Defines number of bytes to display in one line. Default value is 16 bytes.

udp_port

Returns udp logging port.

target_auto_flushing

Returns status of the auto-flushing for the logging target.

RSAREG EVENTS

Check the usage in the Getting Started chapter [here](#).

class Events

Common Events class. Event-related methods and properties. Here you can set all the event handlers.

property before_query_handler: Callable

Returns the handler of before_query events.

Returns

current before_query_handler

property before_write_handler: Callable

Returns the handler of before_write events.

Returns

current before_write_handler

property io_events_include_data: bool

Returns the current state of the io_events_include_data See the setter for more details.

property on_read_handler: Callable

Returns the handler of on_read events.

Returns

current on_read_handler

property on_write_handler: Callable

Returns the handler of on_write events.

Returns

current on_write_handler

sync_from(source: Events) → None

Synchronises these Events with the source.

CHAPTER

TEN

INDEX

Symbols

[SOURCE<HW>]:AREGenerator:CHANnel:INPut:NOMGain,	141
125	[SOURCE<HW>]:AREGenerator:RADar:LSensitivity,
[SOURCE<HW>]:AREGenerator:CHANnel:INPut:RELLevel,	137
125	[SOURCE<HW>]:AREGenerator:RADar:OTA:OFFSet,
[SOURCE<HW>]:AREGenerator:CHANnel:OUTPut:NOMGain,	142
126	[SOURCE<HW>]:AREGenerator:RADar:POWer:INDicator,
[SOURCE<HW>]:AREGenerator:OBject:ALL:[STATE],	143
127	[SOURCE<HW>]:AREGenerator:UNITs:ANGLE, 143
[SOURCE<HW>]:AREGenerator:OBject<CH>:ATTenuation,	[SOURCE<HW>]:AREGenerator:UNITs:DOPPler, 143
127	[SOURCE<HW>]:AREGenerator:UNITs:RANGE, 143
[SOURCE<HW>]:AREGenerator:OBject<CH>:RANGE,	[SOURCE<HW>]:AREGenerator:UNITs:RCS, 143
128	[SOURCE<HW>]:AREGenerator:UNITs:SHIFt, 143
[SOURCE<HW>]:AREGenerator:OBject<CH>:RCS, 128	[SOURCE<HW>]:AREGenerator:UNITs:SPEEd, 143
[SOURCE<HW>]:AREGenerator:OBject<CH>:[SUBChannel<SI>]:DOPPler:FREQuency,	[SOURCE<HW>]:FREQuency:[CW], 147
130	[SOURCE<HW>]:FREQuency:[CW]:RCL, 147
[SOURCE<HW>]:AREGenerator:OBject<CH>:[SUBChannel<SI>]:DOPPler:[SPEEd],	[SOURCE<HW>]:MODulation:[ALL]:[STATE], 149
131	[SOURCE<HW>]:POWer:SPC:MEASure, 151
[SOURCE<HW>]:AREGenerator:OBject<CH>:[SUBChannel<SI>]:[STATE],	[SOURCE<HW>]:POWer:SPC:SINGLE, 152
132	[SOURCE<HW>]:POWer:[LEVEL]:[IMMediate]:RCL,
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:CONNECT,	150
133	[SOURCE]:BB:PATH:COUNT, 146
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:REMOVE:EXECute,	[SOURCE]:INPut:TRIGGer:SLOPe, 148
134	[SOURCE]:PATH:COUNT, 149
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECONDary:ADD,	[SOURCE]:ROSCillator:EXTernal:FREQuency, 153
135	[SOURCE]:ROSCillator:EXTernal:RFOFF:[STATE],
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECONDary:EXECute,	154
136	[SOURCE]:ROSCillator:EXTernal:SBANDwidth, 153
[SOURCE<HW>]:AREGenerator:OSETup:MULTiinstrument:SECONDary<SI>:REMOVE,	[SOURCE]:ROSCillator:SOURCE, 152
136	[SOURCE]:ROSCillator:[INTERNAL]:ADJust:VALUE,
[SOURCE<HW>]:AREGenerator:RADar:ANTenna:CUSTOM:[STATE],	155
138	[SOURCE]:ROSCillator:[INTERNAL]:ADJust:[STATE],
[SOURCE<HW>]:AREGenerator:RADar:ANTenna:REG:GAIN:RX,	155
139	
[SOURCE<HW>]:AREGenerator:RADar:ANTenna:REG:GAIN:TX,	abbreviated_max_len_ascii (ScpiLogger attribute),
139	272
[SOURCE<HW>]:AREGenerator:RADar:BASE:ATTenuation,	abbreviated_max_len_bin (ScpiLogger attribute),
140	272
[SOURCE<HW>]:AREGenerator:RADar:DBYPass:[STATE],	abbreviated_max_len_list (ScpiLogger attribute),
141	272
[SOURCE<HW>]:AREGenerator:RADar:EIRP, 141	
[SOURCE<HW>]:AREGenerator:RADar:EIRP:SENsor,	B
	bin_line_block_size (ScpiLogger attribute), 272

C

CALibration:ALL:[MEASure], 44
 CALibration:DATA:EXPort, 44
 CALibration:DATA:FACTory:DATE, 45
 CALibration:DElay:MINutes, 47
 CALibration:DElay:SHUTdown:[STATe], 48
 CALibration:DElay:[MEASure], 47
 CALibration:FREquency:SWPoints, 48
 CALibration:ROSCillator:DATA:MODE, 50
 CALibration:ROSCillator:STORE, 51
 CALibration:ROSCillator:[DATA], 50
 CALibration:SElected:[MEASure], 52
 CALibration:TSElected:CATalog, 52
 CALibration:TSElected:STEP, 52
 CALibration:TSElected:[MEASure], 52
 CALibration<HW>:ALL:DATE, 43
 CALibration<HW>:ALL:INformation, 43
 CALibration<HW>:ALL:TEMP, 43
 CALibration<HW>:ALL:TIME, 43
 CALibration<HW>:CONTinueonerror, 42
 CALibration<HW>:DATA:UPDate, 45
 CALibration<HW>:DATA:UPDate:LEVel:FORCe, 46
 CALibration<HW>:DEBug, 42
 CALibration<HW>:LEVel:ATTenuator:STAGe, 49
 CALibration<HW>:LEVel:STATe, 49
 clear_cached_entries() (*ScpiLogger method*), 272
 clear_relative_timestamp() (*ScpiLogger method*), 272

D

default_mode (*ScpiLogger attribute*), 271
 DEvice:PRESet, 53
 DEvice:SETTings:BACKup, 54
 DEvice:SETTings:REStore, 55
 device_name (*ScpiLogger attribute*), 271
 DIAgnostic:INFO:OTIME, 61
 DIAgnostic:INFO:OTIME:SET, 61
 DIAgnostic:INFO:POCount, 62
 DIAgnostic:INFO:POCount:SET, 62
 DIAgnostic:SErvice, 65
 DIAgnostic<HW>:BGInfo, 56
 DIAgnostic<HW>:BGInfo:CATalog, 56
 DIAgnostic<HW>:DEBug:PAGE, 57
 DIAgnostic<HW>:DEBug:PAGE:CATalog, 57
 DIAgnostic<HW>:EEPRom<CH>:BIDentifier:CATalog, 59
 DIAgnostic<HW>:EEPRom<CH>:CUSTomize, 59
 DIAgnostic<HW>:EEPRom<CH>:DATA:POINts, 60
 DIAgnostic<HW>:EEPRom<CH>:DELeTe, 58
 DIAgnostic<HW>:POINt:CATalog, 63
 DIAgnostic<HW>:POINt:CONFIguration, 64
 DIAgnostic<HW>:SErvice:SFUNction, 65
 DIAgnostic<HW>:[MEASure]:POINt, 63
 DISPlay:ANNotation:AMPLitude, 68

DISPlay:ANNotation:FREquency, 68
 DISPlay:ANNotation:[ALL], 67
 DISPlay:BRIGhtness, 66
 DISPlay:BUTTon:BRIGhtness, 69
 DISPlay:DIALog:CLOSe, 70
 DISPlay:DIALog:CLOSe:ALL, 70
 DISPlay:DIALog:ID, 70
 DISPlay:DIALog:OPEN, 70
 DISPlay:FOCUSobject, 66
 DISPlay:MESSage, 66
 DISPlay:PSAVe:HOLDoff, 71
 DISPlay:PSAVe:[STATe], 71
 DISPlay:TOUCH:TIME:CHARge, 72
 DISPlay:UKEY:ADD, 73
 DISPlay:UKEY:NAME, 73
 DISPlay:UKEY:SCPI, 73
 DISPlay:UPDate:HOLD, 74
 DISPlay:UPDate:[STATe], 74

E

error() (*ScpiLogger method*), 272

F

flush() (*ScpiLogger method*), 272
 FORMat:BORder, 75
 FORMat:SREGister, 75
 FORMat:[DATA], 75
 FPANel:KEYBoard:LAYout, 77

G

get_logging_target() (*ScpiLogger method*), 271
 get_relative_timestamp() (*ScpiLogger method*), 272

H

HCOpy:DATA, 77
 HCOpy:DEvice:LANGuage, 78
 HCOpy:FILE:[NAME], 80
 HCOpy:FILE:[NAME]:AUTO, 81
 HCOpy:FILE:[NAME]:AUTO:DIRectory, 82
 HCOpy:FILE:[NAME]:AUTO:DIRectory:CLEar, 82
 HCOpy:FILE:[NAME]:AUTO:FILE, 83
 HCOpy:FILE:[NAME]:AUTO:STATe, 81
 HCOpy:FILE:[NAME]:AUTO:[FILE]:DAY:STATe, 83
 HCOpy:FILE:[NAME]:AUTO:[FILE]:MONTH:STATe, 84
 HCOpy:FILE:[NAME]:AUTO:[FILE]:NUMBer, 83
 HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFix, 85
 HCOpy:FILE:[NAME]:AUTO:[FILE]:PREFix:STATe, 85
 HCOpy:FILE:[NAME]:AUTO:[FILE]:YEAR:STATe, 86
 HCOpy:IMAGE:FORMat, 86
 HCOpy:REGION, 77
 HCOpy:[EXECute], 79

I

info() (*ScpiLogger method*), 272
 info_raw() (*ScpiLogger method*), 271
 INITiate<HW>: [POWER]: CONTinuous, 87

K

KBOard: LAYout, 88

L

log_status_check_ok (*ScpiLogger attribute*), 272
 log_to_console (*ScpiLogger attribute*), 271
 log_to_console_and_udp (*ScpiLogger attribute*), 271
 log_to_udp (*ScpiLogger attribute*), 271

M

MEMory: HFRee, 95
 MMEMory: CATalog, 92
 MMEMory: CATalog: LENGth, 92
 MMEMory: CDIRectory, 89
 MMEMory: COPY, 89
 MMEMory: DCATalog, 93
 MMEMory: DCATalog: LENGth, 93
 MMEMory: DELeTe, 89
 MMEMory: DRIVes, 89
 MMEMory: LOAD: STATE, 94
 MMEMory: MDIRectory, 89
 MMEMory: MOVE, 89
 MMEMory: MSIS, 89
 MMEMory: RDIRectory, 89
 MMEMory: RDIRectory: RECURSive, 89
 MMEMory: STORe: STATE, 95
 mode (*ScpiLogger attribute*), 271

R

READ<CH>: [POWER], 96
 restore_format_string() (*ScpiLogger method*), 272

S

ScpiLogger (*class in RsAreg.Internal.ScpiLogger*), 271
 SENSE<CH>: UNIT: [POWER], 117
 SENSE<CH>: [POWER]: APERTure: DEFault: STATE, 98
 SENSE<CH>: [POWER]: APERTure: TIME, 99
 SENSE<CH>: [POWER]: CORRection: SPDevice: LIST, 100
 SENSE<CH>: [POWER]: CORRection: SPDevice: SELeCT, 101
 SENSE<CH>: [POWER]: CORRection: SPDevice: STATE, 101
 SENSE<CH>: [POWER]: DIRect, 102
 SENSE<CH>: [POWER]: DISPlay: PERManent: PRIority, 103
 SENSE<CH>: [POWER]: DISPlay: PERManent: STATE, 104
 SENSE<CH>: [POWER]: FILTer: LENGth: AUTO, 105
 SENSE<CH>: [POWER]: FILTer: LENGth: [USER], 106
 SENSE<CH>: [POWER]: FILTer: NSRatio, 107
 SENSE<CH>: [POWER]: FILTer: NSRatio: MTIME, 108
 SENSE<CH>: [POWER]: FILTer: SONCe, 108
 SENSE<CH>: [POWER]: FILTer: TYPE, 109
 SENSE<CH>: [POWER]: FREQuency, 110
 SENSE<CH>: [POWER]: LOGGing: STATE, 111
 SENSE<CH>: [POWER]: OFFSet, 112
 SENSE<CH>: [POWER]: OFFSet: STATE, 113
 SENSE<CH>: [POWER]: SNUMber, 113
 SENSE<CH>: [POWER]: SOURce, 114
 SENSE<CH>: [POWER]: STATus: [DEVice], 115
 SENSE<CH>: [POWER]: SVERsion, 115
 SENSE<CH>: [POWER]: TYPE, 116
 SENSE<CH>: [POWER]: ZERO, 116
 set_format_string() (*ScpiLogger method*), 272
 set_logging_target() (*ScpiLogger method*), 271
 set_logging_target_global() (*ScpiLogger method*), 271
 set_relative_timestamp() (*ScpiLogger method*), 272
 set_relative_timestamp_now() (*ScpiLogger method*), 272
 SLISt: CLear: LAN, 119
 SLISt: CLear: USB, 120
 SLISt: CLear: [ALL], 118
 SLISt: ELEMeNt<CH>: MAPPING, 121
 SLISt: SCAN: LSENSor, 121
 SLISt: SCAN: USENSor, 122
 SLISt: SCAN: [STATE], 121
 SLISt: SENSor: MAP, 123
 SLISt: [LIST], 118
 SOURce<HW>: PRESet, 123
 STATus: OPERation: BIT<BITNR>: CONDition, 159
 STATus: OPERation: BIT<BITNR>: ENABLe, 160
 STATus: OPERation: BIT<BITNR>: NTRansition, 161
 STATus: OPERation: BIT<BITNR>: PTRansition, 162
 STATus: OPERation: BIT<BITNR>: [EVENT], 161
 STATus: OPERation: CONDition, 157
 STATus: OPERation: ENABLe, 157
 STATus: OPERation: NTRansition, 157
 STATus: OPERation: PTRansition, 157
 STATus: OPERation: [EVENT], 157
 STATus: PRESet, 156
 STATus: QUEStionable: BIT<BITNR>: CONDition, 165
 STATus: QUEStionable: BIT<BITNR>: ENABLe, 166
 STATus: QUEStionable: BIT<BITNR>: NTRansition, 167
 STATus: QUEStionable: BIT<BITNR>: PTRansition, 167
 STATus: QUEStionable: BIT<BITNR>: [EVENT], 166
 STATus: QUEStionable: CONDition, 162
 STATus: QUEStionable: ENABLe, 162

STATUS:QUESTIONable:NTRansition, 162
 STATUS:QUESTIONable:PTRansition, 162
 STATUS:QUESTIONable:[EVENT], 162
 STATUS:QUEue:[NEXT], 168
 SYSTem:BEEPer:STATe, 175
 SYSTem:BIOS:VERSIon, 176
 SYSTem:COMMunicate:GPIB:LTERminator, 176
 SYSTem:COMMunicate:GPIB:RESourCe, 176
 SYSTem:COMMunicate:GPIB:[SELF]:ADDReSS, 177
 SYSTem:COMMunicate:HISLip:RESourCe, 178
 SYSTem:COMMunicate:NETWork:IPADdress, 181
 SYSTem:COMMunicate:NETWork:IPADdress:MODE, 181
 SYSTem:COMMunicate:NETWork:MACAdDress, 178
 SYSTem:COMMunicate:NETWork:RESourCe, 178
 SYSTem:COMMunicate:NETWork:REStArT, 183
 SYSTem:COMMunicate:NETWork:STATus, 178
 SYSTem:COMMunicate:NETWork:[COMMON]:DOMain, 179
 SYSTem:COMMunicate:NETWork:[COMMON]:HOSTname, 179
 SYSTem:COMMunicate:NETWork:[COMMON]:WORKgrouP, 179
 SYSTem:COMMunicate:NETWork:[IPADdress]:DNS, 181
 SYSTem:COMMunicate:NETWork:[IPADdress]:GATeway, 181
 SYSTem:COMMunicate:NETWork:[IPADdress]:SUBNet:MASK, 183
 SYSTem:COMMunicate:SCPI:ETHErnet:[ACTive], 184
 SYSTem:COMMunicate:SERial:BAUD, 184
 SYSTem:COMMunicate:SERial:PARity, 184
 SYSTem:COMMunicate:SERial:RESourCe, 184
 SYSTem:COMMunicate:SERial:SBITs, 184
 SYSTem:COMMunicate:SOCKeT:RESourCe, 186
 SYSTem:COMMunicate:USB:RESourCe, 186
 SYSTem:CRASH, 168
 SYSTem:DATE, 187
 SYSTem:DATE:LOCAl, 187
 SYSTem:DATE:UTC, 187
 SYSTem:DEVice:ID, 188
 SYSTem:DEXChange:CATalog, 190
 SYSTem:DEXChange:DEBUg, 190
 SYSTem:DEXChange:DELete, 190
 SYSTem:DEXChange:EXECute, 192
 SYSTem:DEXChange:FORMat, 190
 SYSTem:DEXChange:SELeCt, 190
 SYSTem:DEXChange:TEMPlate:PREDeFined:CATalog, 193
 SYSTem:DEXChange:TEMPlate:PREDeFined:SELeCt, 193
 SYSTem:DEXChange:TEMPlate:USER:CATalog, 193
 SYSTem:DEXChange:TEMPlate:USER:DELete, 193
 SYSTem:DEXChange:TEMPlate:USER:SELeCt, 193
 SYSTem:DEXChange:TRANsaction:STATe, 194
 SYSTem:DFPPrint, 189
 SYSTem:DFPPrint:HISTory:COUNT, 189
 SYSTem:DFPPrint:HISTory:ENTRy, 189
 SYSTem:DID, 168
 SYSTem:ERRor:ALL, 195
 SYSTem:ERRor:CODE:ALL, 196
 SYSTem:ERRor:CODE:[NEXT], 196
 SYSTem:ERRor:COUNT, 195
 SYSTem:ERRor:HISTory, 197
 SYSTem:ERRor:HISTory:CLEar, 197
 SYSTem:ERRor:STATic, 195
 SYSTem:EXTDevices:UPDate, 198
 SYSTem:EXTDevices:UPDate:CHECK, 198
 SYSTem:EXTDevices:UPDate:NEEDed:[STATe], 199
 SYSTem:EXTDevices:UPDate:TSELeCted:CATalog, 199
 SYSTem:EXTDevices:UPDate:TSELeCted:STEP, 199
 SYSTem:FPReset, 200
 SYSTem:GENeric:MSG, 201
 SYSTem:HELP:EXPort, 201
 SYSTem:HELP:HEADers, 201
 SYSTem:HELP:SYNTax, 202
 SYSTem:HELP:SYNTax:ALL, 202
 SYSTem:IDENtification, 203
 SYSTem:IDENtification:PRESet, 203
 SYSTem:IMPorT, 168
 SYSTem:INForMation:SR, 204
 SYSTem:IRESponse, 168
 SYSTem:LANGuage, 168
 SYSTem:LINux:KERNel:VERSIon, 204
 SYSTem:LOCK:NAME, 206
 SYSTem:LOCK:NAME:DETAiled, 206
 SYSTem:LOCK:OWNer, 206
 SYSTem:LOCK:OWNer:DETAiled, 206
 SYSTem:LOCK:RELease, 207
 SYSTem:LOCK:RELease:ALL, 207
 SYSTem:LOCK:REQuest:SHARed, 208
 SYSTem:LOCK:REQuest:[EXCLusive], 207
 SYSTem:LOCK:SHARed:STRing, 208
 SYSTem:LOCK:TIMEout, 205
 SYSTem:MMEMory:PATH, 209
 SYSTem:MMEMory:PATH:USER, 209
 SYSTem:NINForMation, 168
 SYSTem:NTP:HOSTname, 210
 SYSTem:ORESponse, 168
 SYSTem:OSYStem, 168
 SYSTem:PACKage:CHARTdisplay:VERSIon, 210
 SYSTem:PACKage:GUIFramework:VERSIon, 211
 SYSTem:PACKage:QT:VERSIon, 211
 SYSTem:PCIFpga:UPDate, 212
 SYSTem:PCIFpga:UPDate:CHECK, 213
 SYSTem:PCIFpga:UPDate:NEEDed:[STATe], 213

SYSTem:PCIFpga:UPDate:TSElected:CATalog, 214
 SYSTem:PCIFpga:UPDate:TSElected:STEP, 214
 SYSTem:PRESet, 168
 SYSTem:PRESet:ALL, 168
 SYSTem:PRESet:BASE, 168
 SYSTem:PROFiling:HWACcess:DESCRiption, 215
 SYSTem:PROFiling:HWACcess:PDURation, 215
 SYSTem:PROFiling:HWACcess:STATe, 215
 SYSTem:PROFiling:LOGGing:STATe, 216
 SYSTem:PROFiling:MODUle:CATalog, 217
 SYSTem:PROFiling:MODUle:STATe, 217
 SYSTem:PROFiling:RECORD, 217
 SYSTem:PROFiling:RECORD:CLEar, 217
 SYSTem:PROFiling:RECORD:COUNt, 219
 SYSTem:PROFiling:RECORD:COUNt:MAX, 219
 SYSTem:PROFiling:RECORD:IGNore, 217
 SYSTem:PROFiling:RECORD:SAVE, 217
 SYSTem:PROFiling:RECORD:WRAP:STATe, 220
 SYSTem:PROFiling:STATe, 214
 SYSTem:PROFiling:TICK, 220
 SYSTem:PROFiling:TICK:ENABle, 221
 SYSTem:PROFiling:TPOint:CATalog, 222
 SYSTem:PROFiling:TPOint:REStart, 221
 SYSTem:PROtect<CH>:[STATe], 223
 SYSTem:RCL, 168
 SYSTem:REBoot, 224
 SYSTem:RESet, 168
 SYSTem:RESet:ALL, 168
 SYSTem:RESet:BASE, 168
 SYSTem:REStart, 224
 SYSTem:SAV, 168
 SYSTem:SCRpt:ARG, 225
 SYSTem:SCRpt:CMD, 225
 SYSTem:SCRpt:DATA, 225
 SYSTem:SCRpt:DISCard, 226
 SYSTem:SCRpt:RUN, 225
 SYSTem:SECurity:MMEM:PROtect:[STATe], 228
 SYSTem:SECurity:NETWork:AVAHi:[STATe], 229
 SYSTem:SECurity:NETWork:FTP:[STATe], 230
 SYSTem:SECurity:NETWork:HTTP:[STATe], 231
 SYSTem:SECurity:NETWork:RAW:[STATe], 232
 SYSTem:SECurity:NETWork:REMSupport:[STATe], 233
 SYSTem:SECurity:NETWork:RPC:[STATe], 234
 SYSTem:SECurity:NETWork:SMB:[STATe], 235
 SYSTem:SECurity:NETWork:SOE:[STATe], 236
 SYSTem:SECurity:NETWork:SSH:[STATe], 237
 SYSTem:SECurity:NETWork:SWUPdate:[STATe], 238
 SYSTem:SECurity:NETWork:VNC:[STATe], 239
 SYSTem:SECurity:NETWork:[STATe], 237
 SYSTem:SECurity:SANitize:[STATe], 240
 SYSTem:SECurity:SUPolicy, 241
 SYSTem:SECurity:USBStorage:[STATe], 241
 SYSTem:SECurity:VOLMode:[STATe], 242
 SYSTem:SECurity:[STATe], 227
 SYSTem:SHUTdown, 243
 SYSTem:SIMulation, 168
 SYSTem:SRCat, 168
 SYSTem:SRData, 244
 SYSTem:SRData:DELeTe, 244
 SYSTem:SREStore, 168
 SYSTem:SRExec, 244
 SYSTem:SRMode, 168
 SYSTem:SRSel, 168
 SYSTem:SRTIME:STATe, 245
 SYSTem:SRTIME:SYNChronize, 246
 SYSTem:SSAVe, 168
 SYSTem:STARtup:COMPlete, 246
 SYSTem:TIME, 246
 SYSTem:TIME:DSTIME:MODE, 248
 SYSTem:TIME:DSTIME:RULE, 249
 SYSTem:TIME:DSTIME:RULE:CATalog, 249
 SYSTem:TIME:HRTimer:ABSolute, 250
 SYSTem:TIME:HRTimer:ABSolute:SET, 250
 SYSTem:TIME:HRTimer:RELative, 250
 SYSTem:TIME:LOCAl, 246
 SYSTem:TIME:PROTocol, 246
 SYSTem:TIME:UTC, 246
 SYSTem:TIME:ZONE, 251
 SYSTem:TIME:ZONE:CATalog, 251
 SYSTem:TZONE, 168
 SYSTem:ULock, 252
 SYSTem:UNDO:HCLear, 253
 SYSTem:UNDO:HID:SELeCt, 254
 SYSTem:UNDO:HLABle:CATalog, 254
 SYSTem:UNDO:HLABle:SELeCt, 254
 SYSTem:UNDO:STATe, 253
 SYSTem:UPTime, 168
 SYSTem:VERSion, 168
 SYSTem:WAIT, 168

T

target_auto_flushing (*ScpiLogger attribute*), 272
 TEST:DEvICE:INTernal, 257
 TEST:HS, 255
 TEST:LEvEl, 255
 TEST:NRPTriGger, 255
 TEST:PIXel:COLor, 257
 TEST:PIXel:GRADient, 257
 TEST:PIXel:POINtsize, 257
 TEST:PIXel:RGBA, 257
 TEST:PIXel:TEXT, 257
 TEST:PIXel:WINDow, 257
 TEST:PRESet, 255
 TEST:RES:COLor, 260
 TEST:RES:TEXT, 260
 TEST:RES:WIND, 260
 TEST:SERRor:SET, 262

TEST:SERRor:UNSet, [261](#)
TEST:WRITe:RESult, [263](#)
TEST<HW>:REMOte:LOCKout:[STATe], [260](#)
TEST<HW>:SW:SCMD, [262](#)

U

udp_port (*ScpiLogger attribute*), [272](#)